

# SafeNet Authentication Client (Mac)

**Version 10.0 (GA)**

**User Guide**

---

All information herein is either public information or is the property of and owned solely by Gemalto and/or its subsidiaries who shall have and keep the sole right to file patent applications or any other kind of intellectual property protection in connection with such information.

Nothing herein shall be construed as implying or granting to you any rights, by license, grant or otherwise, under any intellectual and/or industrial property rights of or concerning any of Gemalto's information.

This document can be used for informational, non-commercial, internal and personal use only provided that:

- The copyright notice below, the confidentiality and proprietary legend and this full warning notice appear in all copies.
- This document shall not be posted on any publicly accessible network computer or broadcast in any media and no modification of any part of this document shall be made.

Use for any other purpose is expressly prohibited and may result in severe civil and criminal liabilities.

The information contained in this document is provided "AS IS" without any warranty of any kind. Unless otherwise expressly agreed in writing, Gemalto makes no warranty as to the value or accuracy of information contained herein.

The document could include technical inaccuracies or typographical errors. Changes are periodically added to the information herein. Furthermore, Gemalto reserves the right to make any change or improvement in the specifications data, information, and the like described herein, at any time.

**Gemalto hereby disclaims all warranties and conditions with regard to the information contained herein, including all implied warranties of merchantability, fitness for a particular purpose, title and non-infringement. In no event shall Gemalto be liable, whether in contract, tort or otherwise, for any indirect, special or consequential damages or any damages whatsoever including but not limited to damages resulting from loss of use, data, profits, revenues, or customers, arising out of or in connection with the use or performance of information contained in this document.**

**Gemalto does not and shall not warrant that this product will be resistant to all possible attacks and shall not incur, and disclaims, any liability in this respect. Even if each product is compliant with current security standards in force on the date of their design, security mechanisms' resistance necessarily evolves according to the state of the art in security and notably under the emergence of new attacks. Under no circumstances, shall Gemalto be held liable for any third party actions and in particular in case of any successful attack against systems or equipment incorporating Gemalto products. Gemalto disclaims any liability with respect to security for direct, indirect, incidental or consequential damages that result from any use of its products. It is further stressed that independent testing and verification by the person using the product is particularly encouraged, especially in any application in which defective, incorrect or insecure e functioning could result in damage to persons or property, denial of service or loss of privacy.**

© 2010-17 Gemalto. All rights reserved. Gemalto and the Gemalto logo are trademarks and service marks of Gemalto and/or its subsidiaries and are registered in certain countries. All other trademarks and service marks, whether registered or not in specific countries, are the property of their respective owners.

**Product Version:** 10.0 Mac (GA)

**Document Number:** 007-013725-001, Rev A

**Release Date:** March, 2017

---

## Support Contacts

We work closely with our reseller partners to offer the best worldwide technical support services. Your reseller is the first line of support when you have questions about products and services. However, if you require additional assistance you can contact us directly at:

If you encounter a problem while installing, registering or operating this product, please make sure that you have read the documentation. If you cannot resolve the issue, contact your supplier or Gemalto Customer Support. Gemalto Customer Support operates 24 hours a day, 7 days a week. Your level of access to this service is governed by the support plan arrangements made between Gemalto and your organization. Please consult this support plan for further information about your entitlements, including the hours when telephone support is available to you.

| Contact Method                  | Contact Information   |
|---------------------------------|---|
| Customer Support Portal         | <a href="https://supportportal.gemalto.com">https://supportportal.gemalto.com</a><br>Existing customers with a Technical Support Customer Portal account can log in to manage incidents, get the latest software upgrades, and access the Gemalto Knowledge Base. |
| Technical Support contact email | <a href="mailto:technical.support@gemalto.com">technical.support@gemalto.com</a>  |

## Additional Documentation

The following publications are available:

- 007-013726-002 SafeNet Authentication Client 10.2 (GA) Administrator Guide
- 007-013724-003 SafeNet Authentication Client 10.2 (GA) Customer Release Notes (CRN)

---

# Table of Contents

|          |   |           |
|----------|---|-----------|
| <b>1</b> | <b>Introduction</b>                                       | <b>7</b>  |
|          | Overview  | 7         |
|          | SafeNet Authentication Client Main Features               | 7         |
|          | What's New  | 8         |
|          | Supported Browsers  | 9         |
|          | Supported Platforms                                       | 9         |
|          | Supported Tokens and Smart Cards                          | 9         |
|          | <b>Certificate-based USB Tokens</b>                       | <b>9</b>  |
|          | <b>Certificate-based Hybrid USB Tokens</b>                | <b>9</b>  |
|          | <b>Software Tokens</b>                                    | <b>9</b>  |
|          | <b>Smart Cards</b>  | <b>10</b> |
|          | <b>End-of-Sale Tokens/Smart Cards</b>                     | <b>10</b> |
|          | End-of-Life Tokens/Smart Cards                            | 11        |
|          | External Smart Card Readers                               | 11        |
|          | Mobile PKI Bluetooth Readers                              | 11        |
|          | Friendly Admin Password                                   | 12        |
| <b>2</b> | <b>SafeNet Authentication Client User Interfaces</b>      | <b>13</b> |
|          | Overview of SafeNet Authentication Client User Interfaces | 13        |
|          | SafeNet Authentication Client Tray Icon                   | 14        |
|          | Running the SafeNet Authentication Client Monitor         | 14        |
|          | SAM Tray Menu Functions                                   | 14        |
|          | Opening the SafeNet Authentication Client Tray Menu       | 15        |
|          | Selecting the Token from the SAM Tray Menu                | 15        |
|          | Closing SafeNet Authentication Client Monitor             | 16        |
|          | SafeNet Authentication Client Tools                       | 16        |
|          | SafeNet Authentication Client Tools Toolbar               | 17        |
|          | Opening the Simple View                                   | 18        |
|          | Token Icons   | 19        |
|          | Simple View Functions                                     | 20        |
|          | Opening the Advanced View                                 | 21        |
|          | Advanced View Functions                                   | 22        |
|          | Tokens Node   | 22        |
|          | Selected Token Node                                       | 23        |
|          | Certificate Type Node                                     | 24        |
|          | Common Criteria Certificates                              | 25        |
|          | ECC Certificates  | 25        |
|          | Selected Certificate Node                                 | 26        |
|          | Settings Node   | 27        |

|   |           |
|---|-----------|
| Client Settings Node  | 28        |
| Data Objects Node   | 29        |
| Orphan Objects Node   | 30        |
| <b>3 Token Management</b>                                   | <b>31</b> |
| Selecting the Active Token                                  | 31        |
| Viewing and Copying Token Information                       | 32        |
| Logging On to the Token as a User                           | 32        |
| Renaming a Token  | 33        |
| Changing the Token Password                                 | 34        |
| Unlocking a Token by the Challenge-Response Method          | 36        |
| Deleting Token Content                                      | 38        |
| Importing a Certificate to a Token                          | 39        |
| Importing Common Criteria Certificates                      | 40        |
| Exporting a Certificate from a Token                        | 41        |
| Deleting a Certificate                                      | 42        |
| Logging On to the Token as an Administrator                 | 42        |
| Changing the Administrator Password                         | 43        |
| Setting a Token Password by an Administrator                | 44        |
| <b>4 Token Initialization</b>                               | <b>45</b> |
| Overview of Token Initialization                            | 45        |
| Initializing eToken Devices                                 | 45        |
| Initializing IDPrime based Devices                          | 53        |
| Initializing IDPrime MD Common Criteria Devices             | 54        |
| Initializing IDPrime based Devices (Non Common Criteria)    | 59        |
| <b>5 SafeNet Virtual Tokens</b>                             | <b>64</b> |
| Overview of SafeNet Virtual Products                        | 64        |
| Connecting a SafeNet Virtual Token                          | 65        |
| Disconnecting or Deleting a SafeNet Virtual Token           | 65        |
| Using a SafeNet Virtual Token to Replace a Lost Token       | 66        |
| Unlocking a SafeNet Virtual Token                           | 66        |
| Generating a One-Time Password (OTP)                        | 67        |
| Using a SafeNet Virtual Token on an External Storage Device | 67        |
| <b>6 Common Criteria</b>                                    | <b>68</b> |
| Working with Common Criteria Certified Tokens and Cards     | 68        |
| Unlinked Mode (4 Passwords)                                 | 69        |
| Unlinked Mode Functions                                     | 69        |
| Change Digital Signature PIN                                | 70        |
| Change Digital Signature PUK                                | 71        |
| Set Digital Signature PIN                                   | 72        |
| PKCS#11 Digital Signature PIN Authentication                | 73        |

---

|   |           |
|---|-----------|
| Linked Mode (2 Passwords) . . . . .   | 73        |
| Linked Mode PIN Policy Settings . . . . .   | 74        |
| Operational Differences and Role Protection . . . . .   | 74        |
| <b>7 Client Settings . . . . .</b>  | <b>76</b> |
| Setting Password Quality (eToken devices only) . . . . .  | 76        |
| Allowing Password Quality Configuration on Token after Initialization (eToken devices only) . . . . . | 77        |
| Allowing Only an Administrator to Configure Password Quality on Token (eToken Devices only). . . . .  | 77        |
| Showing the SafeNet Authentication Client Tray Icon . . . . .   | 78        |
| <b>8 Token/Smart Card Settings . . . . .</b>  | <b>79</b> |
| Setting eToken Password Quality (Password Quality Tab) . . . . .                                      | 79        |
| Setting Private Data Caching Mode (Advanced Tab) . . . . .  | 81        |
| Setting IDPrime MD PIN Quality (PIN Quality Tab) . . . . .  | 83        |
| Setting IDPrime MD PIN Properties (Advanced Tab) . . . . .  | 85        |
| <b>9 Licensing . . . . .</b>  | <b>87</b> |
| Viewing and Importing Licenses . . . . .  | 87        |

# Introduction

SafeNet Authentication Client (SAC) is a middleware client that manages Gemalto's extensive SafeNet portfolio of certificate-based authenticators, including eToken, IDPrime smart cards, iKey smart card, USB and software-based devices.

With full backward compatibility and incorporating features from previous middleware versions, SafeNet Authentication Client ensures complete support for all currently deployed eToken and iKey devices, as well as IDPrime MD and .NET smart cards.

## Overview

SafeNet Authentication Client is Public Key Infrastructure (PKI) middleware that provides a secure method for exchanging information based on public key cryptography, enabling trusted third-party verification of user identities. It utilizes a system of digital certificates, Certificate Authorities, and other registration authorities that verify and authenticate the validity of each party involved in an internet transaction.

SafeNet Authentication Client enables the implementation of strong two-factor authentication using standard certificates as well as encryption and digital signing of data. Generic integration with Keychain and PKCS#11 security interfaces enables out-of-the-box interoperability with a variety of security applications offering secure web access, PC and data security, and secure email. PKI keys and certificates can be created, stored, and used securely from within hardware or software.

The SafeNet Authentication Client Tools application and the SafeNet Authentication Client tray icon application are installed with SafeNet Authentication Client, providing easy-to-use configuration tools for users and administrators.

## SafeNet Authentication Client Main Features

SafeNet Authentication Client 10.0 Mac introduces support for IDPrime MD cards, PKCS#11 Multi-Slots as well as PIN quality modifications.

IDPrime MD cards are PKI smart cards. Administrators and users can use and manage IDPrime MD smart cards seamlessly via the standard PKCS#11 interface and without the need for any additional middleware. They offer secure IT Security and ID access and are compatible with the NFC standard.

For more details on the list of Gemalto IDPrime MD cards supported, see *Supported Tokens and Smart Cards* on page 9.

**NOTE:**

The term Token is used throughout the document and is applicable to both Smart Cards and Tokens.

---

## What's New

---

SafeNet Authentication Client 10.0 Mac offers the following new features:

- **Rebranding:** SAC Mac UI and documentation have Gemalto branding.
- **Support for the following IDPrime cards:**
  - IDPrime MD 830-FIPS
  - IDPrime MD 830-ICP
  - IDPrime MD 830 B
  - IDPrime MD 3810 Dual Interface Card
  - IDPrime MD 3810 MIFARE 1K (Contact and Contactless mode)
  - IDPrime MD 3811
- **Support for IDPrime .NET cards**
- **Support for the following IDPrime MD Common Criteria cards:**
  - IDPrime MD 840
  - IDPrime MD 840 B
  - IDPrime MD 3840 - Dual Interface Card
- **Support for SafeNet eToken 5110 Common Criteria**
- **Support for SafeNet eToken 5110 FIPS**
- **Support for unlocking IDPrime MD card range**
- **Friendly Admin Password** - short user friendly passwords are now supported (on IDPrime MD and eToken 5110 CC devices) instead of using 48 hexadecimal digits. For more details, see the SafeNet Authentication Client 10.0 User Guide.
- **Support for PKCS#11 Multi-Slots** - for Common Criteria devices in unlinked mode. For information on how to work with Multi-Slots, see the PKCS#11 Digital Signature PIN section in the SafeNet Authentication Client User Guide.
- **PIN Quality modifications** - for IDPrime MD cards



## Supported Browsers

---

SafeNet Authentication Client 10.0 Mac (GA) supports the following browsers:

- Safari 10.1
- Firefox (up to and including version 52)
- Chrome version 57, for authentication only (does not support certificate enrollment)

## Supported Platforms

---

SafeNet Authentication Client 10.0 Mac (GA) supports the following operating systems:

- OSX 10.11 El Capitan
- OSX 10.12 Sierra

## Supported Tokens and Smart Cards

---

SafeNet Authentication Client 10.0 Mac (GA) supports the following tokens:

### Certificate-based USB Tokens

- SafeNet eToken 5110
- SafeNet eToken 5110 CC
- SafeNet eToken 5110 FIPS
- SafeNet eToken 5110 FIPS HID
- SafeNet eToken 5110 HID

### Certificate-based Hybrid USB Tokens

- SafeNet eToken 7300
- SafeNet eToken 7300-HID

### Software Tokens

- SafeNet Virtual Token
- SafeNet Rescue Token

## Smart Cards

- Gemalto IDPrime MD 840
- Gemalto IDPrime MD 840 B
- Gemalto IDPrime MD 3840
- Gemalto IDPrime MD 3840 B
- Gemalto IDPrime MD 830-FIPS
- Gemalto IDPrime MD 830-ICP
- Gemalto IDPrime MD 830 B
- Gemalto IDPrime MD 3810
- Gemalto IDPrime MD 3811
- Gemalto IDPrime .NET (only SAC PKCS#11 and IDGo 800 Minidriver interfaces).

**NOTE:**

For more information on IDPrime MD Smart Cards, see the IDPrime MD Configuration Guide.

---

## End-of-Sale Tokens/Smart Cards

- SafeNet eToken 5100/5105
- SafeNet eToken 5200/5205
- SafeNet eToken 5200/5205 HID
- SafeNet eToken 4100
- SafeNet eToken 7000 (SafeNet eToken NG-OTP)

**NOTE:**

SafeNet HID tokens are not compatible with Smart Card Logon and CAPI based VPN applications).

---

## End-of-Life Tokens/Smart Cards

- SafeNet eToken PRO 32K v4.2B
- SafeNet eToken PRO 64K v4.2B
- SafeNet eToken Pro SC 32K v4.2B
- SafeNet eToken Pro SC 64K v4.2B
- SafeNet eToken 7100 (SafeNet eToken NG-Flash)
- SafeNet iKey: 2032, 2032u, 2032i (Windows and Mac only)
- SafeNet smart cards: SC330, SC330u, SC330i
- SafeNet eToken 5000 (iKey 4000)
- SafeNet eToken 4000 (SC400)
- SafeNet eToken PRO Java 72K
- SafeNet eToken PRO Anywhere
- SafeNet eToken PRO Smartcard 72K

## External Smart Card Readers

SafeNet Authentication Client 10.0 Mac supports the following smart card readers:

- Gemalto IDBridge K30
- Gemalto IDBridge K50
- Gemalto IDBridge CT30
- Gemalto IDBridge CT40
- Gemalto IDBridge CL 3000 (ex Prox-DU)
- SCR 3310 v2 Reader
- Athena AESDrive IIIe USB v2 and v3
- Advanced Card System ACR 1281U
- Athena Keyboard
- Omnikey 3121
- Dell Broadcom
- Unotron

**NOTE:**

SC Reader drivers must be compatible with the extended APDU format in order to be used with RSA-2048.

## Mobile PKI Bluetooth Readers:

- SafeNet Reader CT1100
- SafeNet Reader K1100

## Friendly Admin Password

The Friendly Admin Password feature permits the use of a short password instead of an admin key made up of 24 binary bytes or 48 Hexadecimal digits.

IDGo 800 UI and SAC 10.0 UI require a 48 Hexadecimal PIN to be entered.


The Friendly Admin Password (known as Friendly Admin) works with all IDPrime devices.

The Friendly Admin uses a user secret (a text password in the range of 8 to 32 ASCII7 characters) to derive a 24 byte long Admin Key.

### For IDPrime CC devices (840 / 3840 / eToken 5110 CC):

When working in linked mode (Chapter 6: Working with Common Criteria Certified Tokens and Cards (page 68)) the Digital Signature PUK is derived from the Admin Key. This is not part of the Friendly Admin feature, but can be used together.

The password sizes: 24 bytes and 48 hexadecimal digits are maintained for backward compatibility with SAC 10.0 and IDGo 800.



# SafeNet Authentication Client User Interfaces

This section describes the SafeNet Authentication Client Mac user interfaces.

**NOTE:**

- If a customized version of SafeNet Authentication Client is installed, the graphics you see may be different from those displayed in this guide.
- In some instances, the word **Password** is replaced by **PIN** or **Passcode**.
- The term Token is used throughout the document and is applicable to both Smart Cards and Tokens.

## Overview of SafeNet Authentication Client User Interfaces

Administrators use SafeNet Authentication Client Tools to set token policies. Users use SAC Tools to perform basic token management functions, such as changing passwords and viewing certificates on the tokens. In addition, SAC Tools provides users and administrators with a quick and easy way to import digital certificates and keys between a computer and a token.

SAC Tools includes an initialization feature allowing administrators to initialize tokens according to specific organizational requirements or security modes, and a password quality feature, which sets parameters to calculate a token password quality rating.

SAC Tools provides information about the token, including its identification and capabilities. It has access to information stored on the token such as keys and certificates, and enables management of content, such as password profiles.

**NOTE:**

Do not remove the device from the USB port during an operation. This may cause corruption of data on the token.




SafeNet Authentication Client provides two user interfaces:

- SafeNet Authentication Client Tray Icon
  - for quick access to several token operations
- SafeNet Authentication Client Tools
  - provides information about each connected token, including its identification and capabilities.
  - can access information stored on each connected token, such as keys and certificates.
  - enables management of token content, such as password policy.

## SafeNet Authentication Client Tray Icon

The SafeNet Authentication Client tray icon offers a shortcut menu to several token operations.

The SafeNet Authentication Client tray icon is displayed as follows:

| No Tokens Connected   | One Token Connected   | Multiple Tokens Connected   |
|---|---|---|
|  |  |  |

## Running the SafeNet Authentication Client Monitor

The SafeNet Authentication Client tray icon is displayed only when the SafeNet Authentication Client Monitor is running.



### NOTE:

If SafeNet Authentication Client is open and the tray icon is not displayed, see Chapter 7: *Showing the SafeNet Authentication Client Tray Icon*, on page 78.

### To open SafeNet Authentication Client on Mac:

- From the Mac desktop, select **Go > Applications > SafeNet > SafeNet Authentication Client > SafeNet Authentication Client**.

## SAM Tray Menu Functions

The following functions can be accessed quickly by right-clicking the tray menu:

- Tools:** opens *SafeNet Authentication Client Tools*.
- About:** displays product version information and license information, and enables license import.
- Token selection:** allows you to select one of the connected tokens to be the active token. This function is available only when more than one token is connected.
- Change Token Password:** opens the *Change Password* window for the selected token. See Chapter 3: *Changing the Token Password*, on page 34.
- Token:** opens the *Token* window for the selected token. See Chapter 3: *Unlocking a Token by the Challenge-Response Method*, on page 36.
- Exit:** closes SafeNet Authentication Client and the tray icon.

The following functions may be displayed, depending on the configuration of your system:

- **Delete Token Content:** removes the deletable data from the selected token.
- **Generate OTP:** generates an OTP on the selected *SafeNet Virtual token*. This function is available only if the selected SafeNet Virtual token is configured to support this function.

## Opening the SafeNet Authentication Client Tray Menu

**To access the shortcut menu from the SafeNet Authentication Client tray icon:**

- Right-click the SafeNet Authentication Client tray icon.


## Selecting the Token from the SAM Tray Menu

If more than one token is connected, select which token to work with.


**To select from multiple tokens in the tray menu:**

1. Right-click the SafeNet Authentication Client tray icon.

The SafeNet Authentication Client tray menu opens. Among the options, a list is displayed of the names and serial numbers of the connected tokens.



2. Hover the mouse over the required token.  
Options for the selected token are displayed.



3. Select the required option.

## Closing SafeNet Authentication Client Monitor

### To close SafeNet Authentication Client:

1. Right-click the SafeNet Authentication Client tray icon, and from the shortcut menu, select **Exit**.  
A warning message is displayed.
2. Click **OK**.

## SafeNet Authentication Client Tools

Administrators use SafeNet Authentication Client Tools to set token policies. Users use SafeNet Authentication Client Tools to perform basic token management functions, such as changing passwords and viewing certificates on a connected token. In addition, SafeNet Authentication Client Tools provides users and administrators with a quick and easy way to import keys from a computer to a token, and to transfer digital certificates between a computer and a token.

SafeNet Authentication Client Tools allows administrators to initialize tokens according to specific organizational requirements or security modes. It includes a password quality feature that sets parameters to calculate a token password quality rating.



### CAUTION:

Do not disconnect a token from the USB port, or a smart card from the reader, during an operation. This can corrupt the data on the token or smart card.

SafeNet Authentication Client Tools includes two viewing options:

- **Simple view:** to perform common tasks  
See "Opening the Simple View" on page 18.
- **Advanced view:** for extensive control over SafeNet Authentication Client and your connected tokens  
See "Opening the Advanced View" on page 21.

Each view displays two panes:







- The left pane indicates which token (*Simple* view) or which object (*Advanced* view) is to be managed.
- The right pane enables the user to perform specific actions to the selected token or object.

A toolbar at the top of the window enables certain actions to be initiated in both views.



## SafeNet Authentication Client Tools Toolbar

A toolbar is displayed at the top of the SafeNet Authentication Client Tools window, in both *Simple* and *Advanced* views. The toolbar contains the following icons:

| Icon   | Action  |
|--|---|
|   | <b>Advanced View</b> – switches from the <i>Simple</i> to the <i>Advanced</i> view                      |
|   | <b>Simple View</b> – switches from the <i>Advanced</i> to the <i>Simple</i> view                        |
|   | <b>Refresh</b> – refreshes the data for all connected tokens  |
|   | <b>About</b> – displays product version information and license information, and enables license import |
|   | <b>Help</b> – opens the <i>Help</i> feature   |
|  | <b>Home</b> – opens the company website   |


## Opening the Simple View

When SafeNet Authentication Client Tools is opened, the *Simple* view is displayed.

### To open SafeNet Authentication Client Tools:

Do one of the following:

- Right-click the SafeNet Authentication Client tray icon, and from the shortcut menu, select **Tools**.  
The *SafeNet Authentication Client Tools* window opens in the *Simple* view.











#### NOTE:


If a customized version of SafeNet Authentication Client is installed, the graphics you see may be different from those displayed in this guide.

When at least one token is connected, an icon representing each connected token is displayed in the left pane. The selected token is marked by a shaded rectangle.

## Token Icons

The icon displayed indicates the type of token that is connected.

| Icon  | Token Type  |  |
|---|---|--|
|    | <ul style="list-style-type: none"> <li>eToken NG-Flash</li> <li>SafeNet eToken 5100/5105 (SafeNet eToken PRO)</li> <li>SafeNet Virtual Token (without OTP support)</li> <li>SafeNet eToken 5110</li> <li>SafeNet eToken 5110 FIPS</li> <li>SafeNet eToken 5110 CC</li> <li>SafeNet eToken 5200/5205 HID</li> <li>iKey: 2032, 2032u, 2032i</li> <li>iKey 4000</li> </ul> |  |
|    | <ul style="list-style-type: none"> <li>SafeNet eToken 5200/5205 (SafeNet eToken PRO Anywhere)</li> <li>SafeNet eToken 7200 (SafeNet eToken NG-Flash Anywhere)</li> </ul>  |  |
|    | <ul style="list-style-type: none"> <li>SafeNet eToken NG-OTP</li> <li>SafeNet Virtual Token (with OTP support)</li> </ul>   |  |
|  | <ul style="list-style-type: none"> <li>SafeNet Virtual Temp Token</li> </ul>  |  |
|  | <ul style="list-style-type: none"> <li>SafeNet Rescue Token</li> </ul>  |  |
|  | <ul style="list-style-type: none"> <li>Smart Card reader – no card connected</li> </ul>   |  |
|  | Smart Card reader – card connected: <ul style="list-style-type: none"> <li>SafeNet eToken 4100 (eToken PRO Smart Card)</li> <li>SafeNet SC330</li> <li>SafeNet SC400</li> <li>IDPrime MD 830-FIPS</li> <li>IDPrime MD 830-ICP</li> <li>IDPrime MD 3810</li> </ul>   |  |
|   | See <i>Supported Tokens and Smart Cards</i> on page 9 for the full list of supported Smart Cards.   |  |
|  | <ul style="list-style-type: none"> <li>Token with corrupted data</li> </ul>   |  |

| Icon (Cont.)  | Token Type (Cont.)  |
|---|---|
|  | <ul style="list-style-type: none"> <li>Unknown token</li> </ul> |

## Simple View Functions

In the right pane, select an enabled button to perform the action described:

| Function                         | Description   |
|----------------------------------|---|
| Rename Token                     | Sets a new name for the token   |
| Change Token Password            | Changes the token password  |
| Token                            | Unblocks the token and resets the token password  |
| Delete Token Content             | Removes deletable data from the token (enabled by default)                                      |
| View Token Info                  | Provides detailed information about the token   |
| Disconnect SafeNet Virtual Token | Disconnects the SafeNet Virtual Token or SafeNet Rescue Token, with an option to also delete it |

## Opening the Advanced View

The SafeNet Authentication Client Tools *Advanced* view provides additional token management functions.


### To open the SafeNet Authentication Client Tools Advanced view:

- Do one of the following:
  - Right-click the SafeNet Authentication Client tray icon, and from the shortcut menu, select **Tools**.
  - From the Mac desktop, select **Go > Applications > SafeNet > SafeNet Authentication Client > SafeNet Authentication Client Tools**.

The *SafeNet Authentication Client Tools* window opens in the *Simple* view.

- Click the **Advanced View** icon.

The *SafeNet Authentication Client Tools* window opens in the *Advanced* view.



The left pane provides a tree view of the different objects to be managed. The tree expands to show objects of the connected tokens.

## Advanced View Functions

You can access the advanced functions by selecting the required object from the left pane in the Tools Advanced View window.

### To access the Advanced functions:


1. In the SafeNet Authentication Client Tools *Advanced* view window, expand the tree in the left pane to display the required object.

The relevant functions are displayed in the right pane.



2. Do one of the following:
  - In the left pane, right-click the object, and select the required function from the shortcut menu.
  - In the left pane, select the object.  
In the right pane, click the appropriate icon, or select the required tab.

## Tokens Node

When you select the *Tokens* node in the left pane, the list of connected devices is displayed in the right pane, and icons are displayed above them.



The following functions are available:

| Function  | Icon  | Right-Click Menu Item         |
|---|---|-------------------------------|
| Reader Settings   |  | Reader Settings               |
| Connect SafeNet Virtual Token<br>See Chapter 5: <i>Connecting a SafeNet Virtual Token</i> , on page 65. |  | Connect SafeNet Virtual Token |











## Selected Token Node

The token names are displayed in the left pane. When you select a token name, the following occurs:


- Information about the token is displayed in the right pane, and function icons are displayed above it
- The name of the token reader is displayed in the tool-tip

Right-click a token name to open a drop-down menu of the functions available for that token.

The following user functions are available:

| User Function   | Icon  | Right-Click Menu Item        |
|---|---|------------------------------|
| Initialize Token<br>See Chapter 4: <i>Token Initialization</i> , on page 45.  |    | Initialize Token             |
| Log On to Token<br>See Chapter 3: <i>Logging On to the Token as a User</i> , on page 32.  |  | Log On to Token              |
| Import Certificate<br>See Chapter 3: <i>Importing a Certificate to a Token</i> , on page 39.  |  | Import Certificate           |
| Change Password<br>See Chapter 3: <i>Changing the Token Password</i> , on page 34.  |  | Change Password              |
| Rename Token<br>See Chapter 3: <i>Renaming a Token</i> , on page 33.  |  | Rename                       |
| Disconnect SafeNet Virtual Token<br>(Enabled for SafeNet Virtual Token or SafeNet Rescue Token only)<br>See Chapter 5: <i>Disconnecting or Deleting a SafeNet Virtual Token</i> , on page 65. |  | Disconnect                   |
| Copy to Clipboard<br>See Chapter 3: <i>Viewing and Copying Token Information</i> , on page 32.  |  | (None)                       |
| Change Digital Signature PIN<br>See Chapter 6: <i>Change Digital Signature PIN</i> (page 70)  |  | Change Digital Signature PIN |
| Change Digital Signature PUK<br>See Chapter 6: <i>Change Digital Signature PUK</i> (page 71)  |  | Change Digital Signature PUK |
| Set Digital Signature PIN<br>See Chapter 6: <i>Set Digital Signature PIN</i> (page 72)  |  | Set Digital Signature PIN    |



 **NOTE:** Depending on the token type, additional options may be displayed in the dropdown menu.

Some administrator functions are available only if an Administrator Password has been set for the token. The administrator icons are located on the right side of the window, enclosed within a border:



See Chapter 3: *Logging On to the Token as an Administrator*, on page 42.




 **NOTE:** Administrator functions are not supported by iKey devices. The `option` is available on iKey devices that were initialized using BSec with the `keys`. After an iKey device is locked the `option` becomes available.

## Certificate Type Node

If the selected token contains certificates, one or two of the following *Certificate Type* nodes are displayed in the left pane under the token's node:



- User Certificates
- Administrator (ECC)
- Certificate Authority Certificates (CA)
- Common Criteria Certificates (CC)

When you select a *Certificate Type* node, a list of the appropriate certificates on the token is displayed in the right pane.





Depending on the certificate type, the following functions may be available:

| User Function  | Icon  | Right-Click Menu Item                                  |
|--|---|--|
| Import Certificate<br>See Chapter 3: <i>Importing a Certificate to a Token</i> , on page 39. |  | Import Certificate                                     |
| Reset Default Certificate Selection  |  | Reset Default Certificate Selection.<br>(Windows only) |

A node for each certificate is displayed in the left pane under the *Certificate Type* node.

## Common Criteria Certificates


Common Criteria (CC) Certificates are supported by eTokens and Gemalto IDPrime MD cards.

Common Criteria certified devices require a common criteria certificate to be imported onto the token/card. This provides an extra authentication layer for digital signing purposes.

See Chapter 3: “Importing Common Criteria Certificates” on page 40.

The following devices support CC:

- SafeNet eToken 5110 CC
- SafeNet eToken 5100 CC
- Gemalto IDPrime MD 840
- Gemalto IDPrime MD 840 B
- Gemalto IDPrime MD 3840
- Gemalto IDPrime MD 3840 B



## ECC Certificates


ECC Certificates are supported by eTokens and Gemalto IDPrime MD cards.

The following devices support ECC:




- eToken PRO Java 72K ECC
- SafeNet eToken 5110, 5110 HID
- Gemalto IDPrime MD 830-FIPS
- Gemalto IDPrime MD 830-ICP
- Gemalto IDPrime MD 830 B
- Gemalto IDPrime MD 3810
- Gemalto IDPrime MD 3810 MIFARE 1K
- Gemalto IDPrime MD 3811
- Gemalto IDPrime MD 840 B

## Selected Certificate Node

When you select a certificate under the *User certificates*, *CA certificates*, or *CC certificates* node, information about the certificate is displayed in the right pane.




Some or all of the following functions are available:

| User Function  | Icon  | Right-Click Menu Item                      |
|--|---|--|
| Delete Certificate<br>See "Deleting a Certificate" on page 42.               |  | Delete Certificate                         |
| Export Certificate<br>See "Exporting a Certificate from a Token" on page 41. |  | Export Certificate                         |
| Set as Default   | (None)  | Set as Default.<br>(Windows only)          |
| Set as Auxiliary   | (None)  | Set as Auxiliary.<br>(Windows only)        |
| Copy to Clipboard<br>See "Viewing and Copying Token Information" on page 32. |  | (None)                                     |
| Set as KSP / Set as CSP  | (None)  | Set as KSP / Set as CSP.<br>(Windows only) |

## Settings Node

Each connected device has a *Settings* node. Select it to see the settings in the right pane.



The following tabs exist for eToken devices:

- Password Quality  
See Chapter 8: Setting eToken Password Quality (Password Quality Tab) (page 79).
- Advanced  
See Chapter 8: Setting Private Data Caching Mode (Advanced Tab) (page 81).



### NOTE:


The *Advanced* tab is not used for iKey devices.

The following tabs exist for IDPrime MD and eToken 5110 CC devices:

- PIN Properties  
See Chapter 8: Setting IDPrime MD PIN Quality (PIN Quality Tab) (page 83)
- Advanced  
See Chapter 8: Setting IDPrime MD PIN Properties (Advanced Tab) (page 85)

## Client Settings Node

Even when no tokens are connected, the left pane includes a *Client Settings* node. Select it to view your computer's *SafeNet Authentication Client Settings* in the right pane.



The changes you make to the *Client Settings* window will affect all tokens that will be initialized using this computer after the changes have been saved.


Like the *Settings* window, the *Client Settings* window contains two tabs:

- Password Quality
- Advanced

See Chapter 7: *Client Settings*, on page 76.


## Data Objects Node

Tokens used with Entrust applications have a *Data Objects* node which contains PKCS#11 data objects.




### To view the contents of a data object:

1. In the left pane, under the token's node, expand the **Data Objects** node.  
Details of all the data objects (**Name**, **Type**, and **Size**) are displayed in the right pane.
2. Select a data object.  
The contents of the data object (**Value Name** and **Value Type**) are displayed in the right pane.



**To delete a data object:**


1. Select the value to be deleted.
2. Click the **Delete Data Object** icon .


**Orphan Objects Node**

An orphan object is a certificate without its key or a key without its certificate. A token's *Orphan Objects* node displays these objects.

**To view a token's orphan objects:**

1. In the left pane, under the token's node, expand the **Orphan Objects** node.
  2. Select an orphan object.
- The certificate data or the key data of the orphan object is displayed in the right pane.

**To delete an orphan object:**

1. Right-click the Orphan Object on the left, and select **Delete**.
2. Click the **Delete Orphan Object** icon .

# Token Management

SafeNet Authentication Client Tools and the SafeNet Authentication Client tray menu enable you to control the use of your tokens.

When running a management task, ensure that the appropriate token remains connected until the process completes!

**NOTE:**

If a customized version of SafeNet Authentication Client is installed, the graphics you see may be different from those displayed in this guide.

## Selecting the Active Token

If more than one token is connected, select which token to work with.

**To set a token as the active token from the SafeNet Authentication Tools window:**

1. Open SafeNet Authentication Client Tools.  
See Chapter 2: *Opening the Simple View*, on page 18 or *Opening the Advanced View* on page 21.
2. In the left pane, select the required token.

**To set a token as the active token from the tray icon:**

1. Right-click the SafeNet Authentication Client tray icon.  
The SafeNet Authentication Client tray menu opens.
2. Select the required token from the tray menu by hovering over the relevant token name. A sub-menu appears displaying a list of tasks that can be performed on the active token.
3. Select the relevant option from the sub-menu.

## Viewing and Copying Token Information


### To view and copy token information:

1. To use the *Simple* view to view token information, do the following:
  - a. Open SafeNet Authentication Client Tools *Simple* view.  
See "Opening the Simple View" on page 18.
  - b. In the left pane, select the required token.
  - c. In the right pane, select **View Token Info**.
  - d. Continue with step 3.
2. To use the *Advanced* view to view token information, do the following:
  - a. Open SafeNet Authentication Client Tools *Advanced* view.  
See "Opening the Advanced View" on page 21.
  - b. In the left pane, select the node of the required token.
  - c. Continue with step 3.
3. The *Token Information* is displayed.  
The information displayed varies according to the type of token.



#### NOTE:

The *Unlocking Codes retries remaining* field for iKey devices is displayed only when the token is locked.

4. To copy the token information to the clipboard, do one of the following:
  - In the *Token Information* window, click **Copy**.
  - In *Advanced* view, click the **Copy to Clipboard** icon: 
5. To paste the copied token information, click the cursor in the target application, and paste the information.
6. Click **OK**.

## Logging On to the Token as a User

You must log on to the token before you can use or change its token content.


### To log on as a user:

1. Open SafeNet Authentication Client Tools *Advanced* view.  
See "Opening the Advanced View" on page 21.



#### NOTE:

If the **Log Off from Token** icon or the **Log Off** option is displayed, you are already logged on to the token.

2. Do one of the following:
  - In the left pane, select the node of the required token.  
  
In the right pane, click the **Log On to Token** icon: 
  - In the left pane, right-click the node of the required token, and select **Log On** from the shortcut menu.



- The *Token Logon* window opens.

- Enter the token password, and click **OK**.  
You are logged on to the token.

## Renaming a Token


The token name does not affect the token contents. It is used solely to identify the token.



### TIP:

If you have more than one token, we recommend assigning each one a unique token name.

### To rename a token:

- To use the *Simple* view to rename a token, do the following:
  - Open SafeNet Authentication Client Tools *Simple* view.  
See "Opening the Simple View" on page 18.
  - In the left pane, select the required token.
  - In the right pane, select **Rename Token**.
  - Continue with step .
- To use the *Advanced* view to rename a token, do the following:
  - Open SafeNet Authentication Client Tools *Advanced* view.  
See "Opening the Advanced View" on page 21.
  - Do one of the following:
    - In the left pane, select the node of the required token.
    - In the right pane, click the **Rename Token** icon: 
    - In the left pane, right-click the node of the required token, and select **Rename Token** from the shortcut menu.
  - Continue with step .

The *Token Logon* window opens.
- Enter the token password, and click **OK**.  
The *Token Rename* window opens.
- Enter the new name in the *New token name* field, and click **OK**.  
The new token name is displayed in the *SafeNet Authentication Client Tools* window.

## Changing the Token Password



### TIP:

The term *Token Password* may be replaced by another term (for example, *Token PIN*), depending on your SafeNet Authentication Client configuration.

SafeNet eTokens are supplied with an initial default token password. In most organizations, the initial token password is **1234567890**.

Gemalto IDPrime cards are supplied with an initial default token password: **0000**.

To ensure strong, two-factor security, it is important for the user to change the initial token password to a private password as soon as the new token is received.


When a token password has been changed, the new password is used for all token applications involving the token. It is the user's responsibility to remember the token password. Without it, the token cannot be used. The administrator can set a token's *Password Quality* settings to certain password complexity and usage requirements.



### NOTE:

The token password is an important security measure in safeguarding your company's private information. The best passwords are at least eight characters long, and include upper- and lower-case letters, special characters such as punctuation marks, and numbers appearing in a random order. We recommend against using passwords that can be easily discovered, such as names or birth dates of family members.

### To change a Token's Password:

1. To use the *Simple* view to change the token password, do the following:
  - a. Open SafeNet Authentication Client Tools *Simple* view.  
See "Opening the Simple View" on page 18.
  - b. In the left pane, select the required token.
  - c. In the right pane, select **Change Token Password**.
  - d. Continue with step 4.
2. To use the *Advanced* view to change the token password, do the following:
  - a. Open SafeNet Authentication Client Tools *Advanced* view.  
See "Opening the Advanced View" on page 21.
  - b. Do one of the following:
    - In the left pane, select the node of the required token.  
  
In the right pane, click the **Change Token Password** icon: 
    - In the left pane, right-click the node of the required token, and select **Change Token Password** from the shortcut menu.
  - c. Continue with step 4.

3. To use the tray menu to change the token password, do the following:
  - a. Right-click the SafeNet Authentication Client tray icon.
  - b. If more than one token is connected, hover over the appropriate token.
  - c. Select **Change Token Password**.
  - d. Continue with step 4.
4. The *Change Password* window opens.

5. Enter the current token password in the *Current Token Password* field.

**NOTE:**

If an incorrect password is entered more than a pre-defined number of times, the token becomes locked.

6. Enter a new token password in the *New Token Password* and *Confirm Password* fields.

**NOTE:**

As you type a new password, the password quality indicator on the right displays a percentage score of how well the new password matches the password quality requirements.

7. Click **OK**.  
A message confirms that the token password was changed successfully.
8. Click **OK**.

## Unlocking a Token by the Challenge-Response Method

If an incorrect token password is entered more than a pre-defined number of times, the token becomes locked. Tokens, including SafeNet Virtual Tokens, can be unlocked if, and only if, an Administrator Password was set during initialization.



### NOTE:

The unlock feature is supported by eToken and IDPrime MD devices.

For IDPrime MD CC devices (IDPrime MD CC 840/3840):

- If the device is in unlinked mode, the new user password is used for both the token password and Digital Signature PIN when unblocking a device.
- If the device is in linked mode, with the default administrator password, the feature is disabled.

SafeNet Rescue Token devices cannot be unlocked.



### CAUTION:

The administrator can limit the number of times that a token can be unlocked. If this number is exceeded, the token becomes unusable. If the token is a physical token, it must be initialized. If it is not a physical token, it must be replaced.

When the administrator has access to the user's token, the administrator can unlock the token using the *Set Token Password* feature.

See Chapter 3: *Setting a Token Password by an Administrator*, on page 44.

Another way to unlock the token and set a new token password is to use the *Challenge – Response* authentication method. The user sends the administrator the *Challenge Code* supplied by SafeNet Authentication Client Tools, and then enters the *Response Code* provided by the administrator. The token becomes unlocked, and the new token password set by the user replaces the previous password.

This method requires a management system, such as SafeNet Authentication Manager, that can generate Response Codes.



### NOTE:

In SafeNet Authentication Client version 8.2 (standard mode) and later, the Challenge-Response unlock method supports both SafeNet eTokens and SafeNet iKey devices.

### To unlock a token using the Challenge-Response method:

1. To use the *Simple* view to unlock a token, do the following:
  - a. Open SafeNet Authentication Client Tools *Simple* view. See "Opening the Simple View" on page 18.
  - b. In the left pane, select the required token.
  - c. In the right pane, select **Unlock Token**.
  - d. Continue with step 4.

2. To use the *Advanced* view to unlock a token, do the following:
  - a. Open SafeNet Authentication Client Tools *Advanced* view.  
See "Opening the Advanced View" on page 21.
  - b. Do one of the following:
    - In the left pane, select the node of the required token.  
In the right pane, click the **Unlock** icon.
    - In the left pane, right-click the node of the required token, and select **Unlock** from the shortcut menu.
  - c. Continue with step 4.
3. To use the tray menu to change the token password, do the following:
  - a. Right-click the SafeNet Authentication Client tray icon.
  - b. If more than one token is connected, hover over the appropriate token.
  - c. Select **Unlock Token**.
  - d. Continue with step 4.
4. The *Unlock Token* window opens, displaying a value in the *Challenge Code* field.  
The *Challenge Code* is 16 characters or, if the token was initialized as Common Criteria, 13 characters.

5. Contact your administrator, and provide the administrator with the *Challenge Code* value displayed.

**NOTE:**

To copy the Challenge Code to the clipboard, click the **Copy to Clipboard** icon.

**CAUTION:**

- After providing the Challenge Code to the administrator, **do not** undertake any activities that use the token until you receive the Response Code and complete the unlocking procedure. If any other token activity occurs during this process, it will affect the context of the Challenge – Response process and invalidate the procedure.
- **For Gemalto IDPrime (MD and .Net) devices only** - During the unlock operation any applications that attempt to connect to the device will be suspended until the unlock operation is completed or canceled.

6. The administrator provides you with the *Response Code* to be entered.  
The *Response Code* is 16 characters or, if the token was initialized as Common Criteria, 39 characters.

**NOTE:**

Response Code creation depends on the back-end application being used by the organization. Administrators should refer to the relevant documentation for information on how to generate the Response Code.

7. Enter a new token password in the *New Token Password* and *Confirm Password* fields.
8. If the new password is known to others and must be changed, select **Token Password must be changed on first logon**.
9. Click **OK**.  
A message confirms that the token was unlocked successfully.
10. Click **OK**.

## Deleting Token Content

Objects on your token can include data objects (profiles), keys, and CA or user certificates. Your system configuration determines which objects are deletable.

The *Delete Token Content* function deletes all deletable objects on your token. Non-deletable objects are not removed from the token. The function does not change settings on the token, such as password quality requirements.

The *Delete Token Content* function is less comprehensive than the *Initialize* function which restores a token to its initial state, removing all objects stored on the token since manufacture and resetting the token password. See Chapter 4: *Token Initialization*, on page 45.

### To delete the token content:

1. To use the *Simple* view, do the following:
  - a. Open SafeNet Authentication Client Tools *Simple* view.  
See "Opening the Simple View" on page 18.
  - b. In the left pane, select the required token.
  - c. In the right pane, select **Delete Token Content**.
  - d. Continue with step 3.
2. Depending on the configuration of your system, you can use the tray menu:
  - a. Right-click the SafeNet Authentication Client tray icon.
  - b. If more than one token is connected, hover over the appropriate token.
  - c. Select **Delete Token Content**.
  - d. Continue with step 3.
3. The *Token Logon* window opens.
4. Enter the token password, and click **OK**.  
The *Delete Token Content* window opens, prompting you to confirm the delete action.
5. To continue with the delete process, click **OK**.  
The *Delete Token Content* window opens, confirming that the token content was deleted successfully.
6. Click **OK** to finish.

## Importing a Certificate to a Token

The following certificate types are supported:

- .pfx
- .p12
- .cer

When importing PFX files, the private key and corresponding certificate are imported to the token. The user is asked if the CA certificates should be imported to the token, and the password (if it exists) that protects the PFX file must be entered.


When downloading a certificate to the computer and then importing the certificate to the token, ensure that the certificate is removed from the local store. Then reconnect the token before using the certificate to sign and encrypt mail. This ensures that the certificate and keys used are those stored on the token and not on the computer.



### NOTE:

It is not possible to import a certificate to an SafeNet Rescue Token.

### To import a certificate:


1. Open SafeNet Authentication Client Tools *Advanced* view.  
See "Opening the Advanced View" on page 21.
2. Do one of the following:
  - In the left pane, select the node of the required token.
  - In the right pane, click the **Import Certificate** icon: 
  - In the left pane, right-click the node of the required token, and select **Import Certificate** from the shortcut menu.
3. The *Token Logon* window opens.
4. Enter the token password, and click **OK**.  
The *Certificate Selection* window opens.
5. Select the certificate to import, and click **Open**.
6. If the certificate requires a password, the *Password* window opens.  
Enter the certificate password, and click **OK**.
7. If the certificate is a Common Criteria certificate, the *Import PIN* window opens.  
Enter the token's Import PIN defined during token initialization, and click **OK**.  
The default value is **1234567890**.
8. All requested certificates are imported, and a message confirms that the import was successful.

## Importing Common Criteria Certificates


When importing PFX files, the private key and corresponding certificate are imported to the token. The user is asked if the CA certificates should be imported to the token, and the password (if it exists) that protects the PFX file must be entered.

### To import a common criteria certificate:

1. Open **SafeNet Authentication Client Tools** Advanced view.
2. Do one of the following:
  - a. In the left pane, select the node of the required token.

In the right pane, click the Import Certificate 

- b. In the left pane, right-click the node of the required token, and select **Import Certificate** from the shortcut menu.
3. The **Token Logon** window opens.
4. Enter the token password, and click **OK**.  
The Certificate Selection window opens.
5. Select the certificate to import, and click **Open**.  
The **Certificate Password** window opens.







- Enter the certificate password, and click **OK**.

The **Digital Signature Logon** window opens

The Digital Signature PIN is required as an additional authentication layer for digital signing purposes.




- Enter the **Digital Signature PIN** and click **OK**.
- The certificate is imported, and a message confirms that the import was successful.
- Common Criteria certificates are displayed as follows in the left pane:



## Exporting a Certificate from a Token

### To export a certificate:

- Open SafeNet Authentication Client Tools *Advanced* view.  
See "Opening the Advanced View" on page 21.
  - In the left pane, expand the node of the required token.
  - Do one of the following:
    - Select the required certificate, and click the **Export Certificate** icon:
 
    - Right-click the required certificate, and select **Export Certificate** from the shortcut menu.
- The **Save As** window opens.
- Select the location to store the certificate, enter a file name, and click **OK**.



#### NOTE:

The certificate file must be DER-encoded or Base64, and not PKCS #7.

## Deleting a Certificate

To remove a certificate from a token, follow the procedures below:

### To delete a certificate from a token:

1. Open SafeNet Authentication Client Tools *Advanced* view.  
See "Opening the Advanced View" on page 21.
2. In the left pane, expand the node of the required token.
3. Do one of the following:
  - In the left pane, select the required certificate, and click the **Delete Certificate** icon.
  - In the left pane, right-click the required certificate, and select **Delete Certificate** from the shortcut menu.
4. The *Delete Certificate* window opens.
5. To delete the certificate, click **Yes**. The *Token Logon* window opens.
6. Enter the token password, and click **OK**.  
The *Delete Certificate* window opens, confirming that the certificate was deleted successfully.
7. Click **OK**.

## Logging On to the Token as an Administrator

If an Administrator Password was set on the token during token initialization, and the user forgets the token password, use the Administrator Password to unlock the token by setting a new token password. We recommend initializing all supported tokens with an Administrator Password.



### NOTE:

- IDPrime devices have a built-in administrator role.
- iKey devices do not support administrator functions.

An administrator has limited permissions on a token. No changes to any user information can be made by the administrator, nor can the user's security be affected. The administrator can change only specific data stored on the token only by using the following functions:

- *Changing the Administrator Password* (not supported by iKey devices)
- *Setting a Token Password by an Administrator*
- *Unlocking a Token by the Challenge-Response Method* (not supported by IDPrime and iKey devices)
- *Setting eToken Password Quality (Password Quality Tab)* (not supported by IDPrime devices)
- *Setting IDPrime MD PIN Properties (Advanced Tab)* (not supported by IDPrime devices)
- *To ignore your changes, click Discard.*

**To log on to a token as an administrator:**

1. Open SafeNet Authentication Client Tools *Advanced* view.  
See "Opening the Advanced View" on page 21.
2. Do one of the following:
  - In the left pane, select the node of the required token.  
In the right pane, click the **Log On as Administrator** icon.
  - In the left pane, right-click the node of the required token, and select **Log On as Administrator** from the shortcut menu.
3. The *Administrator Logon* window opens.
4. Enter the token's Administrator Password, and click **OK**.  
You are logged on as an administrator.

## Changing the Administrator Password

If you are logged on to a token as an administrator, you can change the token's Administrator Password.

**NOTE:**

The administrator password must be entered using 48 hexadecimal characters on IDPrime devices.

**To change the Administrator Password:**

1. Open SafeNet Authentication Client Tools *Advanced* view.
2. Do one of the following:
  - In the left pane, select the node of the required token.  
In the right pane, click the *Change Administrator Password* icon.
  - In the left pane, right-click the node of the required token, and select **Change Administrator Password** from the shortcut menu.

The *Change Administrator Password* window opens.

3. Enter the current Administrator Password in the *Current Administrator Password* field.

**NOTE:**

If an incorrect Administrator Password is entered more than a pre-defined number of times, the token becomes locked.

4. Enter the new password in the *New Administrator Password* and *Confirm Password* fields.
5. Click **OK**. A message confirms that the password was changed successfully.
6. Click **OK**.

---

## Setting a Token Password by an Administrator

---

If you are logged on to a token as an administrator, you can unlock the token by setting a new token password.

**NOTE:**

The Unlock Token feature is for eToken devices only, whereas the Set Token Password features is for eToken and IDPrime devices.

---

**To unlock a token by setting a new Token Password:**

1. Open SafeNet Authentication Client Tools *Advanced* view.  
See "Opening the Advanced View" on page 21.
2. Do one of the following:
  - In the left pane, select the node of the required token.  
In the right pane, click the **Set Token Password** icon.
  - In the left pane, right-click the node of the required token, and select **Set Token Password** from the shortcut menu.

The *Administrator Logon* window opens.

3. Enter the Administrator Password, and click **OK**. The *Set Token Password* window opens.
4. Enter a new token password in the *New Password* and *Confirm Password* fields.

**NOTE:**

The new token password must meet Password Quality settings defined for the token.

---

5. Set the *Logon retries before token is locked* field to the required number.
6. Click **OK**.  
A message confirms that the token password was changed successfully.
7. Click **OK**.  
The token is unlocked, and the user can now log on with the new token password.

# Token Initialization

The token initialization process restores a token to its initial state.



**NOTE:**

You cannot use SafeNet Authentication Client to initialize a SafeNet Virtual product.

## Overview of Token Initialization

The token initialization process removes all objects stored on the token since manufacture, frees up memory, and resets the token password. Then the token is initialized with specific settings according to the organizational requirements or security modes.

Typically, initialization is carried out on a token when an employee leaves the company, enabling the token to be issued to another employee. It completely removes the employee's individual certificates and other personal data from the token, preparing it to be used by another employee.

The following data is initialized:

- Token name
- Token Password
- Administrator Password (optional) - not supported by iKey devices
- Maximum number of logon failures allowed
- Requirement to change the token password on the first logon
- Initialization key
- All user-generated data, such as certificates and profiles

Using customizable parameters, you may be able to select specific parameters that will apply to certain tokens. These parameters may be necessary if you wish to use a token for specific applications or if you require a specific token password or Administrator Password on multiple tokens in the organization.

## Initializing eToken Devices

Initializing an eToken device deletes all objects that were created on the device, while it was in use.




**NOTE:**

- Depending on the type of token being initialized, certain settings may not be enabled.
- If a customized version of SafeNet Authentication Client is installed, the graphics you see may be different from those displayed in this guide.
- To initialize an eToken 5110 Common Criteria device, see *Initializing IDPrime MD Common Criteria Devices* on page 54.

### To initialize an eToken device:


1. Open SafeNet Authentication Client Tools *Advanced* view.  
See "Opening the Advanced View" on page 21.
2. Do one of the following:

- In the left pane, select the node of the required token.

In the right pane, click the **Initialize Token** icon: 

- In the left pane, right-click the node of the required token, and select **Initialize Token** from the shortcut menu.

The *Initialization Options* window opens, allowing you to select how to initialize the token.



3. Select either one of the following:

|  |   |
|--|---|
| Preserve the token settings and policies           | Select to keep current token policies and settings.       |
| Configure all initialization settings and policies | Select to change some or all token policies and settings. |

The *Password Settings* window opens.

4. Enter the following:

|   |  |
|---|--|
| Token Name                                    | Enter a name for the token. If no name is entered, a default name is used. In many organizations, the default token name is "My Token".<br>The token name does not affect the token contents. It is used solely to identify the token.   |
| New Token Password                            | Enter a new Token Password.<br>The default password on an eToken device is 1234567890 automatically appears in this field.   |
| Confirm Password                              | Re-enter the password entered above.   |
| Logon retries before token is locked          | Enter the number of times a token password can be entered incorrectly before the token is locked.<br><b>Note:</b> The retry counter will count only passwords that have a valid length.  |
| Token password must be changed on first login | If required, select token password must be changed on first login.   |
| Create Administrator Password                 | Select Create Administrator Password and enter a New Administrator Password. The minimum password length on an eToken device is 4 characters.<br><b>Note:</b> <ul style="list-style-type: none"> <li>Setting an Administrator Password enables certain functions to be performed on the token, such as setting a new token password to unlock a token.</li> <li>iKey tokens do not support Administrator Passwords.</li> </ul> |
| Confirm Password                              | Re-enter the administrator password.   |

|                                      |  |
|--------------------------------------|--|
| Logon retires before token is locked | Enter a numeric value. This counter specifies the number of times the administrator can attempt to log on to the token with an incorrect password before the token is locked. The default setting for the maximum number of incorrect logon attempts is 15   |
| One-factor logon                     | <p>Configures the token without a password.<br/>The default value for this setting is <b>disabled</b>.</p> <p><b>Note:</b></p> <ul style="list-style-type: none"> <li>• Selecting the One-factor logon option disables the Create Token Password and Create Administrator Password fields.</li> <li>• The One-factor logon feature is used by eToken device only.</li> </ul> |

5. Click **Next**.

The *Password Quality Settings* window opens.

6. Complete the fields as follows:

| Field   | Description  |
|---|--|
| Enforce password quality settings (recommended) | Select this option if you want to define password quality settings when initializing a token. When selected, all options in the window become available. |
| Minimum length (characters)                     | Default: 6 characters  |
| Maximum length (characters)                     | Default: 16 characters   |



| Field (Cont.)                     | Description (Cont.)  |
|-----------------------------------|--|
| Minimum usage period (days)       | <p>The minimum period before the password can be changed.<br/>Default: 0 (none)</p> <p>For iKey devices, the periods are rounded up to periods of weeks (7 days), even though the period is displayed in days. For example, if the period is displayed as less than a week, say 6 days, iKey regards it as a week. If the period is more than two weeks, say 15 days, iKey regards it as three weeks.</p>  |
| Maximum usage period (days)       | <p>The maximum period, in days, before which the password must be changed.<br/>Default: 0 (none)</p> <p>For iKey devices, the periods are rounded up to periods of weeks. See row above for more information.</p>  |
| Expiration warning period (days)  | <p>Defines the number of days before the password expires that a warning message is shown.<br/>Default: 0 (none)</p>   |
| History size                      | <p>Defines how many previous passwords must not be repeated.<br/>Default:<br/>For eToken devices - 10<br/>For iKey devices - 6</p>   |
| Maximum consecutive repetitions   | <p>The maximum number of repeated characters that is permitted in the password.<br/>Default: 3<br/>This feature is not supported by iKey devices.</p>  |
| Must meet complexity requirements | <p>Determines the complexity requirements that are required in the token password.</p> <ul style="list-style-type: none"> <li>• <b>At least 2 types:</b> a minimum of 2 complexity rules (out of the 4 shown in the Manual Complexity fields) are enforced.</li> <li>• <b>At least 3 types:</b> a minimum of 3 complexity rules (out of the 4 shown in the Manual Complexity fields) are enforced (Default).</li> <li>• <b>None:</b> Complexity requirements are not enforced.</li> <li>• <b>Manual:</b> Complexity requirements, as set manually in the <i>Manual Complexity</i> settings, are enforced.</li> </ul> |
| Manual Complexity Rules           | <p>For each of the character types (<b>Upper-case letters</b>, <b>Lower-case letters</b>, <b>Numerals</b> and <b>Special characters</b>) select one of the following options:</p> <ul style="list-style-type: none"> <li>• <b>Permitted</b> - Can be included in the password, but is not mandatory (Default).</li> <li>• <b>Mandatory</b> - Must be included in the password.</li> <li>• <b>Forbidden</b> - Must not be included in the password.</li> </ul> <p><b>Note:</b> The <b>Forbidden</b> option is not supported by iKey devices.</p>  |

7. Click **Next**.

If the device is FIPS or Common Criteria, the *FIPS and Common Criteria Settings* window opens.

If the device is not FIPS or Common Criteria, this window will not be displayed.

Use this window to configure certification and common criteria settings.

The screenshot shows the 'SafeNet Authentication Client' window. At the top, there's a title bar with standard Mac window controls. Below the title bar, the text 'SafeNet Authentication Client' is on the left, and the 'gemalto' logo with the tagline 'security to be free' is on the right. The main content area has two checkboxes: 'Enforce FIPS settings (recommended)' which is checked, and 'Enforce Common Criteria settings' which is unchecked. Below these is a section titled 'When importing a Common Criteria certificate to the token, the user must provide a New Import Password.' It contains two text input fields: 'New Import Password:' and 'Confirm Password:'. Below these fields is a label 'Current Language: EN'. Another section is titled 'Set the maximum number of Common Criteria certificates to be stored.' It contains two text input fields: 'Certificates with 1024-bit keys:' with the value '0' and 'Certificates with 2048-bit keys:' with the value '4'. At the bottom of the window, there are four buttons: 'Cancel', '< Back', 'Next >', and 'Finish'.

## 8. Enter the following:

| Field  | Description  |
|--|--|
| Enforce FIPS settings  | Check this options to define FIPS settings.<br><b>FIPS:</b> Federal Information Processing Standards is a U.S. government-approved set of standards designed to improve the utilization and management of computer and related telecommunication systems                               |
| Enforce Common Criteria settings                                     | Check this options to define Common Criteria settings. When selected, the Certificate Import Password and maximum number of certificates for which to reserve space on the token can be set.<br><b>Common Criteria:</b> an international standard for computer security certification. |
| New Import Password  | Enter a New Import Password.<br>Defines the Password that must be entered when a Common Criteria certificate is imported to the token. The minimum Password length is 4 characters. The default value is: <b>1234567890</b> .  |
| Confirm Password   | Re-enter the password entered above.   |
| Set the maximum number of common criteria certificates to be stored: |  |
| Certificates with 1024-bit keys                                      | To reserve adequate space on the token, set the maximum number of Common Criteria certificates with 1024-bit keys that will be imported to the token.<br>Select a number within the range 0 -16.   |

|                                 |  |
|---------------------------------|--|
| Certificates with 2048-bit keys | To reserve adequate space on the token, set the maximum number of Common Criteria certificates with 2048-bit keys that will be imported to the token.<br>Select a number within the range 1- 16. |
|---------------------------------|--|

9. Click **Next**.

The *Optional Cryptography Mechanisms* window opens.

Use this window to configure Cryptography Settings. RSA Authentication settings is for Windows only.

10. Under *Optional cryptography mechanism*, complete the fields as follows:

| Field                    | Description   |
|--------------------------|---|
| OTP Support              | Default: disabled<br>Select to enable OTP support (on compatible tokens).   |
| 2048-bit RSA key support | Default: enabled<br>Select to enable 2048-bit RSA key support (on compatible tokens).   |
| Private data caching     | Default: Always (fastest)<br>To enhance performance, SafeNet Authentication Client caches public information stored on the token. This option defines when private information (excluding private keys on the token) can be cached outside the token. Select one of the following options: <ul style="list-style-type: none"> <li>Always (fastest): Private information is always cached in the application memory. This enables fast performance, as certain information is cached on the host machine. However, this option is less secure than if no cache is allowed.</li> <li>While user is logged on: Private information is cached outside the token as long as the user is logged on to the token. Once the user logs out, all the private data in the cache is erased.</li> <li>Never: Private information is not cached.</li> </ul> |

|   |  |
|---|--|
| <p>RSA key secondary authentication</p>             | <p>The use of secondary authentication is for Windows only.</p> <p>Default: Never</p> <p>An authentication password may be set for an RSA key. Depending on how this option is set, in addition to having the token and knowing its token password, accessing the RSA key may require knowing the password set for that particular key.</p> <p>Having a password for the key is known as <i>secondary authentication</i>. Select one of the following:</p> <ul style="list-style-type: none"> <li>• Always</li> <li>• Always prompt user</li> <li>• Prompt user on application request</li> <li>• Never</li> <li>• Token authentication on application request</li> </ul> <p>For an explanation of these options, see <i>Initializing IDPrime based Devices</i> on page 53.</p> <p>If the token was initialized as Common Criteria and the secondary authentication <i>Always</i>, <i>Always prompt user</i> or <i>Prompt upon application request</i>, then the secondary authentication setting cannot be changed to <i>Never</i> or <i>Token authentication on application request</i>. This limitation applies to Common Criteria certificates only.</p> |
| <p>Manually set the number of reserved RSA keys</p> | <p>Windows only.</p> <p>Default: Disabled</p> <p>Set the number of reserved RSA keys to reserve space in the token memory. This ensures that there will always be memory available for keys.</p>   |

11. Click **Next**.

The *Initialization Key Settings* window opens.

Use this window to configure Default and Next Initialization Settings.

Change the Initialization Key to protect against accidental token re-initialization in the future. If the Initialization Key is changed from the factory-set default value, the user will be required to open the *Initialization Key* window and enter the correct key during future initialization of the token.

12. Under *Default Initialization Key*, complete the fields as follows:

| Field  | Description   |
|--|---|
| Use default initialization key                 | Select this option if the Initialization Key was not changed from its default during the previous token initialization. The factory-set default is used as the key for the current token initialization.  |
| Use this initialization key                    | Enter the Initialization Key configured in the <i>This Value</i> field during the previous token initialization.  |
| Change the key for the next initialization to: | <ul style="list-style-type: none"> <li>• <b>Default:</b> Revert to the factory-set default so that the user is not required to enter an Initialization Key during subsequent token initializations.</li> <li>• <b>Random:</b> If selected, it will never be possible to re-initialize the token.</li> <li>• <b>This Value:</b> Select and confirm a unique key. During subsequent token initializations, the user must enter this key in the <i>Use this Initialization Key</i> field.</li> </ul> |



**NOTE:**

The initialization key minimum length is 4.

## Initializing IDPrime based Devices

The initialization process removes all objects stored on the device since manufacture, freeing up memory, and resetting the token/card password.

The following can be performed during the initialization process:

- All user-generated data, such as certificates and profiles
- All PKCS#11 objects that were created on the token/card, while in use
- Token/card name/label
- Define a user and administrator password (the user password must be according to the card's policy settings).
- Define password quality settings
- Define a Digital Signature PIN and Digital Signature PUK password the password must be according to the card's policy settings (for IDPrime CC and eToken 5110 CC devices). See Chapter 6: Set Digital Signature PIN (page 72)



**NOTE:**


- The screens displayed during the initialization process are available in English localization only.

This section explains how to initialize IDPrime based Common Criteria and Non Common Criteria devices.


# Initializing IDPrime MD Common Criteria Devices

Both eToken 5110 devices and IDPrime based cards that are Common Criteria certified can be initialized using SAC Tools.

To initialize IDPrime MD Common Criteria certified devices (eToken 5110 CC /IDPrime MD Common Criteria):

1. Open SafeNet Authentication Client Tools Advanced view.
2. Do one of the following:
  - a. In the left pane, select the node of the required token/card  
  
In the right pane, click the Initialize Token icon .
  - b. In the left pane, right-click the node of the required device, and select Initialize Token from the shortcut menu.

The **Initialization Options** window opens, allowing you to select how to initialize the device.



Select the following:

|  |  |
|--|--|
| Preserve the token settings and policies           | Select to keep current token policies and settings.  |
| Configure all initialization settings and policies | Select this option to change some/all token policies and settings. Selecting this option will allow you to: <ul style="list-style-type: none"><li>• Create a token password</li><li>• Create an administrator password</li><li>• Enter the default token and administrator passwords</li><li>• Enter Common Criteria passwords (PIN and PUK)</li></ul> |

3. Click **Next**.  
The **Administrator Logon** window opens. This window requires you to enter an **Administrator Password** and a **Digital Signature PUK** to begin the initialization process.

**NOTE:**

- Gemalto IDPrime MD cards that are Common Criteria certified, are in unlinked mode by default.
- The procedures and screens described in this section are based on the fact that your IDPrime MD device is being used for the first time.

The above window is displayed if your token/card is in unlinked mode as it's received from the factory.

The above window is displayed if your token/card is in linked mode.

4. Enter the current Administrator Password and current Digital Signature PUK. The default Administrator Password is 48 zeros. The default Digital Signature PUK is 6 zeros.

Enter the following:

|  |   |
|--|---|
| Use factory default administrator password | <ul style="list-style-type: none"> <li>Select this check-box if the current administrator password is 48 0's. If selected, the Administrator Password field below is shaded showing the default password.</li> <li>Deselect it if the current administrator password is different from the factory default.</li> </ul>        |
| Administrator Password                     | Enter the current administrator password, that's different from the factory default.  |
| Use factory default digital signature PUK  | <ul style="list-style-type: none"> <li>Select this check-box if the current digital signature PUK is 6 zeros (000000). If selected, the Digital Signature PUK field below is shaded showing the default password.</li> <li>Deselect it if the current Digital Signature PUK is different from the factory default.</li> </ul> |
| Digital Signature PUK                      | Enter the current Digital Signature PUK, that's different from the factory default.   |

5. Click **Next**.  
The **Password Settings** window opens.

SafeNet Authentication Client

gemalto  
security to be free

Token Name:

Create Token Password

New Token Password:

Confirm Password:

Logon retries before token is locked:

☐ Token password must be changed on first logon

Create Administrator Password

Confirm Password:

☐ Keep the current administrator password

Current Language: EN

6. Enter the following:

|            |   |
|------------|---|
| Token Name | <p>Enter a name for the token. If no name is entered, a default name is used. In many organizations, the default token name is "My Token".</p> <p>The token name does not affect the token contents. It is used solely to identify the token.</p> |
|------------|---|



|   |  |
|---|--|
| New Token Password                            | <p>The default password is 1234567890 automatically appears in this field.<br/>The default password on an IDPrime MD card is 4 zeros (0000)</p> <p><b>Note:</b> If the device is initialized with the default token/card password, and standard password quality requirements are in effect, the user must select the Token Password must be changed on first logon option. Otherwise the initialization will fail because the default password does not meet the password quality requirements. If the token password must be changed on first logon option is selected, the initialization will succeed and the user will be prompted to create a new password when next logging on with the token/card. The user will be required to set a token password that meets the Password Quality requirements configured in the Settings window.</p> |
| Confirm Password                              | <p>The default password (1234567890) automatically appears in this field.<br/>If the above field was changed, then re-enter the password entered in the 'New Token Password' field.</p>  |
| Logon retries before token is locked          | <p>Enter the number of times a token password can be entered incorrectly before the token is locked.</p> <p>For Common Criteria devices that are in linked mode, the maximum value displayed is 3. When in unlinked mode, the value displayed is 15. This value cannot be changed for both linked and unlinked modes.</p>  |
| Token password must be changed on first logon | <p>If required, select token password must be changed on first logon.</p> <p><b>Note:</b> When initializing a device in Unlinked mode, and this option is selected, both the Token (User) Password and Digital Signature PIN are effected (ensure that both the Token Password and Digital Signature PIN are changed).</p>   |
| PIN Policy                                    | <p>Enables you to set PIN Quality/Property parameters.</p> <p>See Chapter 8: Setting IDPrime MD PIN Quality (PIN Quality Tab) (page 83) and <i>Setting IDPrime MD PIN Properties (Advanced Tab)</i> on page 85</p>   |
| Create Administrator Password                 | <p>If necessary, enter a new administrator password, that's different from the current administrator password. Your current password may be the default password or a different password. Only you know this password.</p> <p>You can change the default Administrator Password to a password that is between 8-32 alphanumeric characters. See Chapter 1: Friendly Admin Password (page 12).</p>  |
| Confirm Password                              | <p>Re-enter the administrator password.</p>  |
| Keep the current administrator password       | <p>Select this if you want to keep the current administrator password.</p> <p><b>Note:</b> If this option is selected, the following warning message appears:<br/>If the current password is the default password (48 0's), it is strongly recommended to update the administrator password to keep your token secure.</p>   |

7. Click **Next**.  
The **IDPrime Common Criteria Settings** window opens.  
The IDPrime Common Criteria Settings window allows you to define Common Criteria passwords, which are made up of a Digital Signature PIN (User Password) and Digital Signature PUK (Administrator Password).  
  
This IDPrime Common Criteria Settings window defines whether you are going to work in linked or unlinked mode.

SafeNet Authentication Client

gemalto  
security to be free

Common Criteria Passwords:  
☐ Use the same token and administrator passwords for digital signature operation

New Digital Signature PIN:

Confirm PIN:

New Digital Signature PUK:

Confirm PUK:

8. To work in inked mode, enter the following:
- |  |   |
|--|---|
| Use the same token and administrator passwords for digital signature operation | Select this option to perform digital signing operations using your current Token and Administrator passwords.<br><b>Note:</b> Selecting this option does not require entering a Digital Signature PIN and Digital Signature PUK. The fields below will be unavailable. |
|--|---|

9. To work in unlinked mode, enter the following:


|                           |   |
|---------------------------|---|
| New Digital Signature PIN | Enter a New Digital Signature PIN. This option allows you to work in 'unlinked' mode.   |
| Confirm PIN               | Re-enter the New Digital Signature PIN.   |
| PIN Policy                | Enables you to set PIN Quality/Property parameters.<br>See Chapter 8: Setting IDPrime MD PIN Quality (PIN Quality Tab) (page 83) and <i>Setting IDPrime MD PIN Properties (Advanced Tab)</i> on page 85 |
| New Digital Signature PUK | Enter a New Digital Signature PUK. This option allows you to work in 'unlinked' mode.   |
| Confirm PUK               | Re-enter the New Digital Signature PUK.   |
| PIN Policy                | Enables you to set PIN Quality/Property parameters.<br>See Chapter 8: Setting IDPrime MD PIN Quality (PIN Quality Tab) (page 83) and <i>Setting IDPrime MD PIN Properties (Advanced Tab)</i> on page 85 |

10. Click **Finish**. A warning message is displayed.
11. Click **OK** when the warning message: **The token initialization process will delete all token content and reset all token parameters** appears.
- The **Token initialized successfully** message is displayed.


## Initializing IDPrime based Devices (Non Common Criteria)

IDPrime cards that are not Common Criteria certified can be initialized using SAC Tools.

To initialize an IDPrime based non Common Criteria device:

1. Open SafeNet Authentication Client Tools Advanced view.
2. Do one of the following:
  - a. In the left pane, select the node of the required token/card  
 In the right pane, click the Initialize Token icon .
  - b. In the left pane, right-click the node of the required device, and select Initialize Token from the shortcut menu.

The **Initialization Options** window opens, allowing you to select how to initialize the device.




Select the following:

|  |  |
|--|--|
| Preserve the token settings and policies           | Select to keep current token policies and settings.  |
| Configure all initialization settings and policies | Select this option to change some/all token policies and settings. Selecting this option will allow you to: <ul style="list-style-type: none"><li>• Create a token password</li><li>• Create an administrator password</li><li>• Enter the default token and administrator passwords</li></ul> |

## 3. Click Next.

The Administrator Logon window opens.

This window requires you to enter an Administrator Password to begin the initialization process

SafeNet Authentication Client 

Enter the current Administrator Password to initialize the Token

☐ Use factory default administrator password

Administrator Password:

Current Language: EN

The default administrator password is a known value of 0's set on the standard profile.  
For the non-default value, please enter it manually.

4. Enter the current Administrator Password. The default Administrator Password is 48 zeros.  
Enter the following:

|  |  |
|--|--|
| Use factory default administrator password | <ul style="list-style-type: none"> <li>• Select this check-box if the current administrator password is 48 0's. If selected, the Administrator Password field below is shaded showing the default password.</li> <li>• Deselect it if the current administrator password is different from the factory default.</li> </ul> |
| Administrator Password                     | Enter the current administrator password, that's different from the factory default.   |

5. Click **Next**.  
The **Password Settings** window opens.

6. Enter the following:

|   |  |
|---|--|
| Token Name                                    | Enter a name for the token. If no name is entered, a default name is used. In many organizations, the default token name is "My Token".<br>The token name does not affect the token contents. It is used solely to identify the token.   |
| New Token Password                            | The default password is 1234567890 automatically appears in this field. The default password on an IDPrime MD card is 4 zeros (0000)<br><b>Note:</b> If the device is initialized with the default token/card password, and standard password quality requirements are in effect, the user must select the Token Password must be changed on first logon option. Otherwise the initialization will fail because the default password does not meet the password quality requirements. If the token password must be changed on first logon option is selected, the initialization will succeed and the user will be prompted to create a new password when next logging on with the token/card. The user will be required to set a token password that meets the PIN Quality requirements. |
| Confirm Password                              | The default password (1234567890) automatically appears in this field. If the above field was changed, then re-enter the password entered in the 'New Token Password' field.   |
| Logon retries before token is locked          | Enter the number of times a token password can be entered incorrectly before the token is locked.  |
| Token password must be changed on first logon | If required, select token password must be changed on first logon.   |
| PIN Policy                                    | Enables you to set PIN Quality/Property parameters.<br>See Chapter 8: Setting IDPrime MD PIN Quality (PIN Quality Tab) (page 83) and <i>Setting IDPrime MD PIN Properties (Advanced Tab)</i> on page 85  |

|   |   |
|---|---|
| Create Administrator Password           | <p>If necessary, enter a new administrator password, that's different from the current administrator password. Your current password may be the default password or a different password. Only you know this password.</p> <p>You can change the default Administrator Password to a password that is between 8-32 alphanumeric characters. See Chapter 1: Friendly Admin Password (page 12).</p> |
| Confirm Password                        | Re-enter the administrator password.  |
| Logon retries before token is locked    | The number of times an administrator password can be entered incorrectly before the token is locked. This parameter appears for non IDPrime Common Criteria devices.  |
| Keep the current administrator password | <p>Select this if you want to keep the current administrator password.</p> <p><b>Note:</b> If this option is selected, the following warning message appears: If the current password is the default password (48 0's), it is strongly recommended to update the administrator password to keep your token secure.</p>  |

7. Click **Finish**. A warning message is displayed.
  8. Click **OK** when the warning message: **The token initialization process will delete all token content and reset all token parameters** appears.
- The **Token initialized successfully** message is displayed.

# SafeNet Virtual Tokens

SafeNet Authentication Client supports the SafeNet Virtual Token line of products. This includes SafeNet Virtual Token and SafeNet Rescue Token devices.

To obtain a SafeNet Virtual Token file, contact your administrator.

## Overview of SafeNet Virtual Products

SafeNet Authentication Client supports tokens from the SafeNet Virtual Token family. These tokens are stored as files on your computer or on an external storage device.

The following types of software tokens are available:

- **SafeNet Rescue Token:** provides a solution when a staff member loses or damages their token when away from the office. A SafeNet Rescue Token is a read-only token which functions for a limited period of time. You cannot import certificates to it.

**NOTE:**

On a Mac System: A SafeNet Rescue Token must be run from a folder where the user has read-write permissions. If not, it will not be recognized by Mac Keychain Access.

- **SafeNet Virtual Token:** performs all the functions of an eToken NG-OTP. It can store the same data, including key pairs and certificates. Its configuration may enable it to support OTP generation.

A SafeNet Virtual Token is “locked” to a particular computer or storage device, such as a flash drive. This means that it can be used only on the computer or storage device on which it was enrolled.

- **SafeNet Virtual Temp Token:** identical to a SafeNet Virtual Token, but its certificates become invalid after a pre-defined time period.



## Connecting a SafeNet Virtual Token

To use your eToken Virtual product as a token, connect its file to SafeNet Authentication Client.

Under certain conditions, the token is connected automatically. See "Using a SafeNet Virtual Token on an External Storage Device" on page 67.

### To connect a SafeNet Virtual device from the file:

1. Double-click the SafeNet Virtual (.etvp) or SafeNet Rescue Token (.etv) file.  
The SafeNet Virtual or SafeNet Rescue Tokens connect to the computer and display a confirmation message.
2. Click **OK**.

### To use SafeNet Authentication Client Tools to connect a SafeNet Virtual Token:

1. Open SafeNet Authentication Client Tools *Advanced* view.  
See "Opening the Advanced View" on page 21.
2. Do one of the following:
  - In the left pane, select the **Tokens** node.  
In the right pane, click the **Connect SafeNet Virtual Token** icon:



- In the left pane, right-click the **Tokens** node, and select **Connect SafeNet VirtualToken** from the shortcut menu.
3. Navigate to the SafeNet Virtual Token file (\*.etvp) or SafeNet Rescue Token file (\*.etv), and double-click it.  
The SafeNet Virtual product is connected.

## Disconnecting or Deleting a SafeNet Virtual Token

For security purposes, disconnect your SafeNet Virtual or SafeNet Rescue Token from its connected reader when you are not using it.

Under certain conditions, the token is disconnected automatically. See "Using a SafeNet Virtual Token on an External Storage Device" on page 67.

When your SafeNet Virtual product is no longer required, disconnect and also delete it. For example, if your SafeNet Rescue Token temporarily replaced a lost token, disconnect and delete it when you receive a permanent replacement token.

### To disconnect or delete a SafeNet Virtual Token:

1. To use the *Simple* view to disconnect, do the following:
  - a. Open SafeNet Authentication Client Tools *Simple* view.  
See "Opening the Simple View" on page 18.
  - b. In the left pane, select the required eToken Virtual or SafeNet Rescue Token.
  - c. In the right pane, select **Disconnect SafeNet Virtual Token** (or **Disconnect**).
  - d. Continue with step .

2. To use the *Advanced* view to disconnect, do the following:

a. Open SafeNet Authentication Client Tools *Advanced* view.  
See "Opening the Advanced View" on page 21.

b. Do one of the following:

- In the left pane, select the node of the required eToken Virtual or SafeNet Rescue Token.  
In the right pane, click the **Disconnect SafeNet Virtual Token** icon:



- In the left pane, right-click the node of the required eToken Virtual or SafeNet Rescue Token, and select **Disconnect** from the shortcut menu.

c. Continue with step .

The *Disconnect SafeNet Virtual Token* window opens.

3. Do one of the following:

- To keep the SafeNet Virtual Token or SafeNet Rescue Token file on the computer or device for later use, click **Disconnect**.  
Only the token connection to SafeNet Authentication Client is disconnected. It can be reconnected later. See "Connecting a SafeNet Virtual Token" on page 65.
- To disconnect the token from SafeNet Authentication Client, and also remove the SafeNet Virtual Token or SafeNet Rescue Token file from the computer, click **Delete**.  
After a SafeNet Virtual Token or SafeNet Rescue Token is deleted, it cannot be reconnected later. A new file must be installed before it can be connected.

## Using a SafeNet Virtual Token to Replace a Lost Token

---

To use a SafeNet Virtual Token or SafeNet Rescue Token to replace a lost token, the SafeNet Virtual Token or SafeNet Rescue Token must be enrolled using SafeNet Authentication Manager.

For more information, refer to the SafeNet Authentication Manager documentation.

## Unlocking a SafeNet Virtual Token

---

If you enter an incorrect password more than a pre-defined number of times, the eToken Virtual becomes locked. To unlock the token, see Chapter 3: *Unlocking a Token by the Challenge-Response Method*, on page 36.



### NOTE:

The number of times that a SafeNet Virtual Token can be locked can be limited to a specific amount. If this number is exceeded, the SafeNet Virtual Token becomes unusable. This function is not available for a SafeNet Rescue Token.

---


## Generating a One-Time Password (OTP)

The **Generate OTP** function is available only if an eToken Virtual or eToken Rescue, with the OTP feature activated, is stored on your computer.

### To generate an OTP:

1. Right-click the SafeNet Authentication Client tray icon.  
The SafeNet Authentication Client tray menu opens.

2. Select **Generate OTP**.  
The *Generate OTP* window opens.



3. Click **Generate OTP**.  
The *Token Logon* window opens.
4. Enter the token password, and click **OK**.  
A unique OTP is generated, and it is displayed in the *Generate OTP* window.
5. Copy the OTP to authenticate yourself to your application.
6. Click **Close** to close the *Generate OTP* window.

## Using a SafeNet Virtual Token on an External Storage Device

The operating system automatically connects an SafeNet Virtual product when all of the following conditions are met:

- The SafeNet Virtual Token file is locked to an external storage device, such as a flash drive.
- The file is located in the `eTokenVirtual` folder on the storage device.
- The storage device is connected to the computer.

When the storage device is removed from the computer, the operating system automatically disconnects the SafeNet Virtual Token that was automatically connected.

If the SafeNet Virtual Token is located on an external storage device in a location other than the `eTokenVirtual` folder, you must connect the SafeNet Virtual Token manually. See "Connecting a SafeNet Virtual Token" on page 65.

Before removing the storage device, you must disconnect the eToken Virtual manually. See "Disconnecting or Deleting a SafeNet Virtual Token" on page 65. Otherwise, the eToken Virtual will be displayed in SafeNet Authentication Client as a token with corrupted data.

For more information about token icons, see Chapter 2: *Token Icons*, on page 19.

# Common Criteria


SafeNet Authentication Client supports Gemalto IDPrime MD Common Criteria (CC) card range and IDPrime .NET cards (See Chapter 1: Supported Tokens and Smart Cards (page 9) for a detailed list of cards), as well as eToken 5110 CC.

## Working with Common Criteria Certified Tokens and Cards

IDPrime MD and eToken devices that are Common Criteria certified are used mainly for digital signing purposes. When working with common criteria certified tokens and cards, 2 additional passwords (Specific to qualified digital signature operations) are required.

SAC allows you to work with Common Criteria certified tokens and cards in two modes:

- Unlinked mode
- Linked mode



## Unlinked Mode (4 Passwords)

Devices are set to work in unlinked mode by default.

To work in unlinked mode, clear the **Use the same token and administrator passwords for digital signature operation** check-box (For more details, see Chapter 4: “Initializing IDPrime MD Common Criteria Devices” on page 54). The following four common criteria device passwords are required when working in unlinked mode:

- **Token Password (Role # 1)** - Used to perform device write/delete and exchange key operations. The default token password is 4 zero characters "0000".
- **Administrator Password (Role # 2)** - Used to /unlock a locked token password, or to perform initialization operations. The default administrator password is 48 Hexadecimal zeros.
- **Digital Signature PIN (Role # 3)** - Used to perform Digital Signature operations with Sign only keys (CC keys). The default Digital Signature PIN is 6 zero characters "000000".
- **Digital Signature PUK (Role # 4)** - Used to /unlock a locked Digital Signature PIN. The default Digital Signature PUK is 6 zero characters "000000".






### NOTE:

- If the device is in unlinked mode, the new user password is used for both the token password and Digital Signature PIN when unblocking a device.
- When initializing a device in unlinked mode and the **Token Password Must be changed at first logon** option is selected, both the Token (User) Password and Digital Signature PIN are effected (ensure that both the Token Password and Digital Signature PIN are changed).

## Unlinked Mode Functions

When in unlinked mode, the following Digital Signing function icons are displayed in SAC Tools advanced view:

| User Function                | Icon  | Right-Click Menu Item        |
|------------------------------|---|------------------------------|
| Change Digital Signature PIN |  | Change Digital Signature PIN |
| Change Digital Signature PUK |  | Change Digital Signature PUK |
| Set Digital Signature PIN    |  | Set Digital Signature PIN    |

## Change Digital Signature PIN

Use this option to change the Digital Signature PIN.

### To change a digital signature PIN:

1. Open SafeNet Authentication Client Tools Advanced view.


Do one of the following:

- a. In the left pane, select the node of the required token.


In the right pane, click the **Change Digital Signature PIN** icon: 

- b. In the left pane, right-click the node of the required token, and select **Change Digital Signature PIN** from the shortcut menu.

The **Change Digital Signature PIN** window opens.



Change Digital Signature PIN:

SafeNet Authentication Client 

Current Digital Signature PIN:

New Digital Signature PIN:

Confirm PIN:

The new PIN must comply with the quality settings defined on the token.

A secure PIN has at least 8 characters, and contains upper-case letters, lower-case letters, numerals, and special characters (such as !, \$, #, %).

Current Language: EN

OK Cancel

2. Enter the **Current Digital Signature PIN**.
  3. Enter the **New Digital Signature PIN**.
  4. Confirm the New Digital Signature PIN and click **OK**.
- The **Password Changed Successfully** window opens.
5. Click **OK**.

## Change Digital Signature PUK

Use this option to change the Digital Signature PUK.

### To change a digital signature PUK:

1. Open SafeNet Authentication Client Tools Advanced view.


Do one of the following:

- a. In the left pane, select the node of the required token.


In the right pane, click the **Change Digital Signature PUK** icon: 

- b. In the left pane, right-click the node of the required token, and select **Change Digital Signature PUK** from the shortcut menu.

The **Change Digital Signature PUK** window opens.



Change Digital Signature PUK:

SafeNet Authentication Client 

Current Digital Signature PUK:

New Digital Signature PUK:

Confirm PUK:

The new PUK must comply with the quality settings defined on the token.

A secure PUK has at least 8 characters, and contains upper-case letters, lower-case letters, numerals, and special characters (such as !, \$, #, %).

Current Language: EN

OK Cancel

2. Enter the **Current Digital Signature PUK**.
3. Enter the **New Digital Signature PUK**.
4. Confirm the New Digital Signature PUK and click **OK**.  
The **Password Changed Successfully** window opens.
5. Click **OK**.

## Set Digital Signature PIN

Use this option to change the Digital Signature PIN using the Digital Signature PUK.

### To set a digital signature PIN:

1. Open SafeNet Authentication Client Tools Advanced view.


Do one of the following:

- a. In the left pane, select the node of the required token.

In the right pane, click the **Change Digital Signature PIN** icon: 


- b. In the left pane, right-click the node of the required token, and select **Set Digital Signature PIN** from the shortcut menu.

The **Digital Signature PUK Logon** window opens.



2. Enter the **Digital Signature PUK** and click **OK**.

The **Set PIN** window opens.



3. Enter a **New Digital Signature PIN**.
4. Confirm the New Digital Signature PIN and click **OK**.  
The **Password Changed Successfully** window opens.
5. Click **OK**.



## PKCS#11 Digital Signature PIN Authentication

For Common Criteria signature compliancy, the Digital Signature PIN must be authenticated before each signing operation. Thus, the PKCS#11 library may prompt the user to enter the Digital Signature PIN.

Logging onto the device is required when a Common Criteria RSA private key operation is performed for the first time using the PKCS#11 library (for example signing operations). With the support of Common Criteria PKCS#11 Multi-Slots (in unlinked mode), all qualified signature functionalities are available via the Common Criteria virtual slot labeled **Digital Signature PIN**, which are associated with PIN Role #3. Thus, in order to use Common Criteria keys, the user must ensure that this Common Criteria slot is selected and used by the application.

The application must then call `C_Login` on the virtual slot as a `CKU_USER` to provide the qualified Digital Signature PIN (PIN role #3).

The device remains in login state unless it was configured otherwise. In this case the user is prompted to enter the Digital Signature PIN when needed.

If the Digital Signature PIN authentication fails, an error message is displayed.

See the SafeNet Authentication Client Administrator Guide for setting Multi-Slot values.

## Linked Mode (2 Passwords)


To work in linked mode, the token/card must be initialized to work in linked mode. Select the **Use the same token and administrator passwords for digital signature operation** check-box (For more details, see Chapter 4: “Initializing IDPrime MD Common Criteria Devices” on page 54) to perform digital signing operations with only a Token and Administrator password.

Working in linked mode, the user enters a Token Password to authenticate for both Digital Signature operations (where a Digital Signature PIN is required) and regular token operations (where a Token Password is required).

The user enters the Administrator Password to authenticate operations that require an Administrator Password or Digital Signature PUK.

**NOTE:**

If the device is in linked mode, with the default administrator password, the feature is disabled.



## Linked Mode PIN Policy Settings

The user password must be compliant with the password quality of the Token Password (Role#1) and the Digital Signature PIN (Role#3) i.e. the password used as the Token Password must be at least 6 digits long and must also be compliant with the password quality settings of the Token Password (Role#1) and the Digital Signature PIN (Role#3).

The password policy of the Digital Signature PUK (Role#4) must be set to minimum i.e. 6 characters long, while other password policies are disabled.

## Operational Differences and Role Protection

The table below displays the differences between eToken 5100 CC and eToken 5110 CC/IDPrime 840 and the roles that protect the specific operation.

| Operation  | eToken 5100 CC   | IDPrime 840/3840 and<br>eToken 5110 CC  |
|--|--|---|
| This column indicates the type of operation performed. | This column indicates which password is required to perform the specified operation on an eToken 5100 CC device. | This column indicates which password is required to perform the specified operation on IDPrime 840/3840 and eToken 5110 CC devices. |
| <b>Initialize</b>                                      | Initialization Key   | Administrator Password  |
| <b>Generate sign only key pair</b>                     | Token Password   | Token Password + Digital Signature PIN  |
| <b>Generate exchange key pair</b>                      | Token Password   | Token Password  |
| <b>Import sign only key pair</b>                       | Import Password  | Token Password + Digital Signature PIN  |

| <b>Operation</b>                        | <b>eToken 5100 CC</b>                                 | <b>IDPrime 840/3840 and<br/>eToken 5110 CC</b>   |
|---|---|--|
| <b>Import exchange key pair</b>         | Token Password  | Token Password   |
| <b>Delete sign only key pair</b>        | Token Password  | Token Password + Digital Signature PIN   |
| <b>Delete exchange key pair</b>         | Token Password  | Token Password   |
| <b>Sign with sign only key pair</b>     | Token Password  | Digital Signature PIN  |
| <b>Sign with exchange only key pair</b> | Token Password  | Token Password   |
| <b>Decrypt</b>                          | Token Password  | Token Password   |
| <b>Unlock</b>                           | Token Password is locked by the Digital Signature PUK | Token Password is locked by the Administrator Password<br>Digital Signature PIN is locked by the Digital Signature PUK |

# Client Settings

*Client Settings* are parameters that are saved to the computer and apply to all tokens that are initialized on the computer after the settings have been configured. Use token settings to determine behavior that applies to a specific token. See Chapter 8: “Token/Smart Card Settings” on page 79.

## Setting Password Quality (eToken devices only)

The *Password Quality* feature enables the administrator to set certain complexity and usage requirements for token passwords.

To set PIN Quality parameters for IDPrime MD cards see Chapter 8: Setting IDPrime MD PIN Quality (PIN Quality Tab) (page 83).



### NOTE:

The token password is an important security measure in safeguarding your company's private information. The best passwords are at least eight characters long, and include upper-case and lower-case letters, punctuation marks, and numerals appearing in a random order.

### To set the Password Quality:

1. Open SafeNet Authentication Client Tools *Advanced* view.  
See "Opening the Advanced View" on page 21.
2. In the left pane, select **Client Settings**.
3. In the right pane, select the **Password Quality** tab.  
The *Password Quality* tab opens.
4. Do one of the following:
  - Change the *Password Quality* settings, and click **Save**.



### TIP:

The Password Quality settings are configured the same way as the Token Password quality settings.  
See Chapter 8: *Setting eToken Password Quality (Password Quality Tab)*, on page 79.

- To ignore your changes, click **Discard**.
- To apply SafeNet Authentication Client's default settings, click **Set to Default**.



### NOTE:

When entering a value in the *Expiry warning period* field, you must make sure that a value is also entered in the *Maximum usage period* field. If no value is entered in the *Maximum usage period* field, an error message appears.

## Allowing Password Quality Configuration on Token after Initialization (eToken devices only)

The *Allow password quality configuration on token after initialization* option determines whether the password quality parameters on the token can be changed after initialization.

**NOTE:**

This feature is not supported by iKey tokens.

### To enable password quality configuration after initialization:

1. Open SafeNet Authentication Client Tools *Advanced* view.  
See "Opening the Advanced View" on page 21.
2. In the left pane, select **Client Settings**.
3. In the right pane, select the **Advanced** tab.
4. Select **Allow password quality configuration on token after initialization**.
5. Do one of the following:
  - To save your changes, click **Save**.
  - To ignore your changes, click **Discard**.

## Allowing Only an Administrator to Configure Password Quality on Token (eToken Devices only)

The *Allow only an administrator to configure password quality on token* option determines whether the password quality parameters on the token can be changed after initialization by the administrator only, and not by the user. This option is selected by default.

### To define who can configure password quality on a token:

1. Open SafeNet Authentication Client Tools *Advanced* view.  
See "Opening the Advanced View" on page 21.
2. In the left pane, select **Client Settings**.
3. In the right pane, select the **Advanced** tab.
4. Do one of the following:
  - To enable configuration by the administrator only, select **Allow only an administrator to configure password quality on token**.
  - To enable configuration by the user also, clear **Allow only an administrator to configure password quality on token**.
5. Do one of the following:
  - To save your changes, click **Save**.
  - To ignore your changes, click **Discard**.

## Showing the SafeNet Authentication Client Tray Icon

---

You can determine whether the SafeNet Authentication Client tray icon is displayed.

### To show the SafeNet Authentication Client tray icon:

1. Open SafeNet Authentication Client Tools *Advanced* view.  
See "Opening the Advanced View" on page 21.
2. In the left pane, select **Client Settings**.
3. In the right pane, select the **Advanced** tab.
4. In the *Show application tray icon* drop-down list, select one of the following:
  - **Never**: The tray icon is never displayed
  - **Always**: The tray icon is always displayed
5. Do one of the following:
  - To save your changes, click **Save**.
  - To ignore your changes, click **Discard**.


# Token/Smart Card Settings

Configurations set in the selected token's *Settings* tab determine behavior that applies to the specific token.

For configurations set in *Client Settings*, that apply the settings to all tokens that are initialized after the settings have been configured, see Chapter 7: *Client Settings*, on page 76.

## Setting eToken Password Quality (Password Quality Tab)

The Password Quality tab enables you to set the device's password policies.



### To set password quality for a token:

1. Open SafeNet Authentication Client Tools *Advanced* view.  
See "Opening the Advanced View" on page 21.
2. In the left pane, expand the node of the required token, and select **Settings**.
3. In the right pane, select the **Password Quality** tab.  
The *Password Quality* tab opens.

## 4. Enter the password quality parameters as follows:

| Password Quality Parameter        | Description  |
|-----------------------------------|--|
| Minimum length (characters)       | Default: 6 characters  |
| Maximum length (characters)       | Default: 16 characters   |
| Maximum usage period (days)       | <p>The maximum period, in days, before which the password must be changed.</p> <p>Default: 0 (none)</p> <p>For iKey devices, the periods are rounded up to periods of weeks (7 days), even though the period is displayed in days. For example, if the period is displayed as less than a week, say 6 days, iKey regards it as a week. If the period is more than two weeks, say 15 days, iKey regards it as three weeks.</p>  |
| Minimum usage period (days)       | <p>The minimum period before the password can be changed.</p> <p>Default: 0 (none)</p> <p>For iKey devices, the periods are rounded up to periods of weeks. See row above for more information.</p>  |
| Expiration warning period (days)  | <p>Defines the number of days before the password expires that a warning message is shown.</p> <p>Default: 0 (none)</p>  |
| History size                      | <p>Defines how many previous passwords must not be repeated.</p> <p>Default: 0</p> <p>For eToken devices - 10</p> <p>For iKey devices - 6</p>  |
| Maximum consecutive repetitions   | <p>The maximum number of repeated characters that is permitted in the password.</p> <p>Default: 3</p> <p>This feature is not supported by iKey devices.</p>  |
| Must meet complexity requirements | <p>Determines the complexity requirements that are required in the token password.</p> <ul style="list-style-type: none"> <li>• <b>At least 2 types:</b> a minimum of 2 complexity rules (out of the 4 shown in the Manual Complexity fields) are enforced.</li> <li>• <b>At least 3 types:</b> a minimum of 3 complexity rules (out of the 4 shown in the Manual Complexity fields) are enforced (Default).</li> <li>• <b>None:</b> Complexity requirements are not enforced.</li> <li>• <b>Manual:</b> Complexity requirements, as set manually in the <i>Manual Complexity</i> settings, are enforced.</li> </ul> |



| Password Quality Parameter | Description (Cont.)  |
|----------------------------|--|
| Manual complexity rules    | <p>For each of the character types (<b>Numerals</b>, <b>Upper-case letters</b>, <b>Lower-case letters</b>, and <b>Special characters</b>) select one of the following options:</p> <ul style="list-style-type: none"> <li>• <b>Permitted</b> - Can be included in the password, but is not mandatory (Default).</li> <li>• <b>Mandatory</b> - Must be included in the password.</li> <li>• <b>Forbidden</b> - Must not be included in the password.</li> </ul> <p><b>Note:</b> The <b>Forbidden</b> option is not supported by iKey devices.</p> |

5. Do one of the following:
- To save your changes, click **Save**.
  - To ignore your changes, click **Discard**.
  - To apply SafeNet Authentication Client's default settings, click **Set to Default**.

## Setting Private Data Caching Mode (Advanced Tab)



### NOTE:

This feature is not supported by iKey, IDPrime MD, .NET and eToken 5110 CC devices.


In SafeNet Authentication Client, public information stored on the token is cached to enhance performance.

This setting defines when private information (excluding private keys on the eToken PRO / NG OTP / smart card) can be cached outside the token.

### To set private data caching mode:

1. Open SafeNet Authentication Client Tools *Advanced* view.  
See "Opening the Advanced View" on page 21.
2. In the left pane, expand the node of the required token, and select **Settings**.
3. In the right pane, select the **Advanced** tab.

The *Advanced* tab opens.




4. In the *Private data caching* field, select one of the following options:

| Option                  | Description  |
|-------------------------|--|
| Always (fastest)        | Always caches private information in the application memory. This enables fast performance, as certain information is cached on the host machine. However, this option is less secure than if no cache is allowed. |
| While user is logged on | Caches private data outside the token as long as the user is logged on to the token. Once the user logs off, all the private data in the cache is erased.  |
| Never                   | Does not cache private data.   |

5. Do one of the following:
- To save your changes, click **Save**.
  - To ignore your changes, click **Discard**.

## Setting IDPrime MD PIN Quality (PIN Quality Tab)

The PIN Quality tab provides parameters which define the rules that must be respected in order for the PIN to be accepted.



### NOTE:

In the MD Manager, the unlimited value = FFh

In SAC Tools, the unlimited value = 00h

For IDPrime cards, the following PIN Quality parameters exist:

| PIN Quality Parameter   | Description   |
|---|---|
| Minimum length (characters)                                       | The minimum value that can be set for the length of a PIN's value. This value must be in the range 04h - 40h for a local PIN and 04h - 10h for the global PIN.  |
| Maximum length (characters)                                       | The maximum value that can be set for the length of a PIN's value. This value must be in the range 04h - 40h for a local PIN and 04h - 10h for the global PIN. This value must be equal to or greater than the PIN Min. length value. |
| History size  | Number of previous PIN values that cannot be matched by a new PIN. Range is 00h-0Ah.<br>00h = No history  |
| Number of different characters that can be repeated at least once | The number of different characters that can be repeated at least once. Range is 00h-FFh.<br>00h = No limitation   |
| Maximum number of times a character can appear                    | The maximum number of times a character can appear. Range is 00h-FFh.<br>00h = No limitation  |

| PIN Quality Parameter   | Description (Cont.)  |
|---|--|
| Maximum number of character in a sequence                       | <p>Max length of characters sequences e.g. 1,2,3,4 or a,b,c,d. Range is 00h-FFh.</p> <p>(For example: If set to 4, 1,2,3,4,a,5 is allowed, but 1,2,3,4,5,a is not allowed).</p> <p>00h = No limitation</p>   |
| Maximum number of times a character can be repeated in adjacent | <p>Maximum number of times that characters can be adjacent. Range is 00h-FFh.</p> <p>00h = No limitation</p> <p>01h = Repeated characters cannot be adjacent</p>   |
| Manual complexity rules   | <p>For each of the character types (<b>Numeric, Alpha upper, Alpha lower, Alpha, non alpha, Non ASCII</b>)</p> <ul style="list-style-type: none"> <li>• Numeric = 30h...39h</li> <li>• Alpha upper = 41h...5Ah</li> <li>• Alpha lower = 61h...7Ah</li> <li>• Alpha = 41h...5Ah + 61h...7Ah</li> <li>• Non alpha = 20h...2Fh + 3Ah...40h + 5Bh...60h + 7Bh...7Fh</li> <li>• Non ASCII = 80h...FFh?</li> </ul> |


## Setting IDPrime MD PIN Properties (Advanced Tab)

The PIN Advanced tab enables you to define PIN properties that must be met in order for the PIN to be accepted. The PIN Advanced tab is available for all IDPrime based devices.

Select **Settings** in the left pane, to view the User PIN Quality/Advanced fields in the right pane.

Select **Digital Signature PIN** in the left pane, to view the Digital Signature PIN Quality/Advanced fields in the right pane.

Select **Digital Signature PUK** in the left pane, to view the Digital Signature PUK Quality/Advanced fields in the right pane.



For IDPrime MD cards, the following PIN Property parameters exist in the Advanced Tab:

| PIN Property Parameter | Description  |
|------------------------|--|
| PIN Type               | <ul style="list-style-type: none"> <li>Regular PIN - Use the keyboard to enter a PIN</li> <li>External PIN - Use an external keyboard/key pad</li> </ul>   |
| PIN Purpose            | <p>Defines the purpose of the PIN. This property is for information only.</p> <p>The following options are available:</p> <ul style="list-style-type: none"> <li>Authentication PIN</li> <li>Digital Signature PIN</li> <li>Encryption PIN</li> <li>Non Repudiation PIN</li> <li>Administrator PIN</li> <li>Primary Card PIN</li> <li>Unlock Only PIN</li> </ul> |
| Cache Type             | Read only field  |
| Cache Info             | Read only field  |

| PIN Property Parameter           | Description (Cont.)   |
|----------------------------------|---|
| PIN Flags                        | <p>These flags are for backward compatibility only.</p> <ul style="list-style-type: none"> <li>No Flags</li> <li>Required Security Entry</li> </ul>   |
| Ext. PIN Flags                   | <p>The following options are available:</p> <ul style="list-style-type: none"> <li>No Flags - PINs are considered as follows: <ul style="list-style-type: none"> <li>Regular PIN &amp; Normal Reader ==&gt; Regular PIN</li> <li>Regular PIN &amp; PIN Pad Reader ==&gt; External PIN</li> <li>External PIN &amp; Normal Reader ==&gt; Regular PIN</li> <li>External PIN &amp; PIN Pad Reader ==&gt; External PIN</li> </ul> </li> <li>No Regular fallback - changes the third case as follows: <ul style="list-style-type: none"> <li>External PIN &amp; Normal Reader ==&gt; Login refused</li> </ul> </li> <li>No Auto PIN Pad - changes the second case as follows: <ul style="list-style-type: none"> <li>Regular PIN &amp; PIN Pad Reader ==&gt; Regular PIN</li> </ul> </li> <li>No Regular fallback + No Auto PIN Pad (both of the above).</li> </ul> |
| <b>PIN Validity Parameter:</b>   |   |
| Validity period (days)           | <p>The maximum period, in days, before the PIN must be changed. When the PIN expires, the user is forced to change the PIN value the next time that the PIN is presented.</p> <p>Default: 0 (no validity period)</p>  |
| Expiration warning period (days) | <p>Defines the number of days before the PIN expires that a warning message is shown.</p> <p>Default: 0 (no warning)</p>  |

**NOTE:**

PIN Quality and PIN Property settings may also be accessed when Initializing a device. See Chapter 4: Initializing IDPrime based Devices (page 53).

# Licensing

Import a SafeNet license for your SafeNet Authentication Client installation.

## Viewing and Importing Licenses

SafeNet Authentication Client installations that do not have a SafeNet license can be used for evaluation only, and a message is displayed on all logon windows.


You can view your licenses and import new ones using the SafeNet Authentication Client *About* window.

### To view and import licenses:

1. Do one of the following:
  - Right-click the SafeNet Authentication Client tray icon, and from the shortcut menu, select **About**.
  - Open SafeNet Authentication Client Tools.  
See "Opening the Advanced View" on page 21.  
On the toolbar, click the **About** icon:



The *About* window opens, displaying your license information in the *License Information* box.



2. To import a new license, select **Import New License**.  
The *Import License* window opens.
3. Do one of the following:
  - If the SafeNet license box is automatically filled, click **OK**.
  - Copy your new SafeNet license string to the license box, and click **OK**.
  - Click **Import from File**, browse to the file containing your license, open it to copy its contents to the license box, and click **OK**.
  - The *About* window opens, displaying your updated license information in the *License Information* box.